Getting Started with MAINVIEW[®] for DB2[®] and RxD2TM

MAINVIEW[®] for DB2[®] 7.1 RxD2[™] 2.1

Version 7.1

April 30, 2001



Copyright © 1992-2001 BMC Software, Inc., as an unpublished work. All rights reserved.

BMC Software, the BMC Software logos, and all other BMC Software product or service names are registered trademarks or trademarks of BMC Software, Inc. IBM and DB2 are registered trademarks of International Business Machines Corp. All other registered trademarks or trademarks belong to their respective companies.

Restricted Rights Legend

U.S. GOVERNMENT RESTRICTED RIGHTS. UNPUBLISHED–RIGHTS RESERVED UNDER THE COPYRIGHT LAWS OF THE UNITED STATES. Use, duplication, or disclosure by the U.S. Government is subject to restrictions set forth in FAR Section 52.227-14 Alt. III (g)(3), FAR Section 52.227-19, DFARS 252.227-7014 (b), or DFARS 227.7202, as amended from time to time. Send any contract notices to Contractor/Manufacturer:

BMC Software, Inc. 2101 CityWest Blvd. Houston TX 77042-2827 USA

Contacting BMC Software

You can access the BMC Software Web site at http://www.bmc.com. From this Web site, you can obtain general information about the company, its products, special events, and career opportunities. For a complete list of all BMC Software offices and locations, go to http://www.bmc.com/corporate/offices.html.

USA and (Canada	Outside USA and Canada			
Address	BMC Software, Inc. 2101 CityWest Blvd.	Telephone	(01) 713 918 8800		
	Houston TX 77042-2827	Fax	(01) 713 918 8000		
Telephone	713 918 8800 or 800 841 2031				
Fax	713 918 8000				

Customer Support

You can obtain technical support by using Response OnlineTM (comprehensive information from the Web) or Response On DemandTM. To expedite your inquiry, please see "Before Contacting BMC Software," below.

Response Online

You can obtain technical support from BMC Software 24 hours a day, seven days a week by accessing the technical support Web site at http://www.bmc.com/support.html. From this site, you can

- read overviews about support services and programs that BMC Software offers
- find the most current information about BMC Software products
- search a database for problems similar to yours and possible solutions
- order or download product documentation
- report a problem or ask a question
- subscribe to receive e-mail notices when new product versions are released
- find worldwide BMC Software support center locations and contact information, including e-mail addresses, fax numbers, and telephone numbers

Response On Demand

In the USA and Canada, if you need technical support and do not have access to the Web, call 800 538 1872. Outside the USA and Canada, please contact your local support center or your local sales office for assistance.

Before Contacting BMC Software

Before you contact BMC Software, have the following information available so that a technical support analyst can begin working on your problem immediately:

- product information
 - product name
 - product version (release number)
 - license number and password (trial or permanent)
- · operating-system and environment information
 - machine type
 - operating system type, version, and service pack or program temporary fix (PTF)
 - system hardware configuration
 - serial numbers
 - related software (database, application, and communication) including type, version, and service pack or PTF
- sequence of events leading to the problem
- · commands and options that you used
- messages received (and the time and date that you received them)
 - product error messages
 - messages from the operating system, such as file system full
 - messages from related software

Contents

Chapter 1. Quick Reference Card	
Where to Start.	
How to Activate Requests.	4
	_
Chapter 2. Isolating DB2 Performance Problems	
Enter MAINVIEW	
Check DB2 Status and Activity	
Check Status of All DB2s	
Current Thread Activity	
Exceptions Overview	
Thread Activity for Multiple DB2s	
Analyze One DB2	
Check DB2 Status	
Buffer Pools	17
Lock Contention Analysis	19
Page Set Status and I/O Analysis	22
Use Monitors to Isolate Problems	26
Start a Monitor	27
Review Critical Problems	30
Exceptions	31
Warning Overview	32
More Detailed Information	33
Windows-Mode Monitor Views	35
Workload Objective Views	37
Audit Trail	38
Issue DB2 Commands	40
Chapter 3. Monitoring a DB2 Data Sharing Group	41
Define the Group Context.	
Check Current Group Activity	
Look at Page Set Considerations (I/O / GBP-DEP)	
Analyze Global Lock Contention	
Tune Group Buffer Pools	
Chapter 4. Tuning an Application with Trace	59
Start an Application Trace	
Specify Options	
Activate the Trace	
Review Tips on Tracing Tests.	
Look for Application Problems	
**	
All trace entries (DDZ Accounting Records)	
All Trace Entries (DB2 Accounting Records)	
Data for One Thread	
Data for One Thread	73
Data for One Thread	73
Data for One Thread View DB2 Accounting Data. View Detail Event Summaries (Detail Trace Only). Another Thread.	73
Data for One Thread View DB2 Accounting Data. View Detail Event Summaries (Detail Trace Only). Another Thread Detail Events	73 76 82
Data for One Thread View DB2 Accounting Data. View Detail Event Summaries (Detail Trace Only) Another Thread Detail Events Summarized Data for All Threads	73 76 82 83
Data for One Thread View DB2 Accounting Data. View Detail Event Summaries (Detail Trace Only). Another Thread Detail Events Summarized Data for All Threads Application I/O Analysis.	73 76 82 83 85
Data for One Thread View DB2 Accounting Data. View Detail Event Summaries (Detail Trace Only) Another Thread Detail Events Summarized Data for All Threads	73 76 82 83 85 86

Chapter 5. Analyzing the DB2 Workload with Trace	. 93
Analyze Recent Workload History	. 94
Graphic Display of Thread History	. 94
Workload Analysis	
Isolating Problems	
Review Past History	
Current Log Data Set	
Earlier Log Data Set	
Analyze DB2 I/O	
Run a System I/O Trace	
Analyze I/O by Page Set	
Analyze I/O by Application	
Print Workload Reports	106
Chapter 6. Using RxD2 with MAINVIEW for DB2	
Improve Performance with SQL Prototyping	
Start a Trace	
Test a Statement	
EXPLAIN a Statement	
Compare Test Results	
Print Results	
Access DB2 Catalog and PLAN_TABLE Information	
Accessing the RxD2 Primary Option Menu	
·	
Accessing EXPLAIN from a Trace	
Accessing Other Catalog Data with Direct Hyperlinks	
Accessing Specific Objects in the Catalog	130
Chapter 7. Printing Reports	135
Print Online Reports	
History Traces (Thread Data)	
All Data per Traced Thread	
Other Accounting Report Examples	
Other Detail Trace Report Examples	
Online Views	
Print Offline Reports	
Batch Trace Print	
Trace Print from a TLDS.	
Trace Print from SMF Records	
Performance Reporter Reports	
Reports from SMF	
Reports from DB2 Tables	
•	
Index	153

About This Book

This tutorial is intended for first-time users of MAINVIEW for DB2 and RxD2. It takes you step-by-step through practice sessions with several fundamental product applications.

Note: You will need appropriate DB2 authorization to execute certain steps.

Conventions Used in This Book

The following syntax notation is used in this tutorial:

- Items you type and keys you press are highlighted with **bold** letters.
- An item in CAPITAL LETTERS must be entered exactly as shown.
- Items in lowercase letters are values you supply.
- A vertical line | separates alternative options; one must be chosen.

The term pop-up refers to an ISPF pop-up display that replaces the original screen image.

Chapter 1. Quick Reference Card

This chapter contains a quick reference card for your use. You can tear it out and keep it by your terminal if you wish.

It contains

- A brief list of where you should start looking when you want information about a certain topic
- Examples for defining requests

Important

If you are a new user, be sure to go through each of the practice sessions in the rest of this book before using the quick reference card.

Quick Reference Card

MAINVIEW for DB2

Where to Start

To See	Start Here
DB2 Primary Option Menu	Option 5 on MAINVIEW Selection Menu
Multiple DB2s	EZDSSI Easy Menu
One DB2	EZDB2 Easy Menu
Applications analysis	EZDBA Easy Menu
Tuning wizards	EZDWIZ Easy Menu
All windows-mode views	MAIN (or VIEWS) view
A full-screen-mode service from windows mode	or TRANsfer target product; service Examples: TRAN DB2P DB2; LOG or TRAN DB2P DB2; EX LOCKD
A windows-mode view from full-screen mode	Option V or TRANsfer target MVDB2; view
Status of all DB2s	STDB2 view
Detail status of one DB2	STDB2D view or DB2ST (Option 1) (full-screen mode)
Current threads	THDACTV view or USERS (full-screen mode)
Current locks	LOCKD or LOCKU (full-screen mode)
Lock contention analysis	Lock Analysis tuning wizard (WZLOCK view)
Data sharing analysis	Data Sharing tuning wizard (WZDSHAR view)
Page sets	EZDPS Easy Menu
I/O analysis	EZDPS Easy Menu or Option 7 (full-screen mode)
Buffer pools	EZDBFRPL Easy Menu
Group buffer pools	EZDSSI / EZDBFRPL Easy Menus or Data Sharing tuning wizard (WZDSHAR view)
Monitors	EZDB2 / EZDSSI Easy Menus
Workload objectives	EZDB2 / EZDSSI Easy Menus
Current traces	Option 4 (full-screen mode)
History traces	Option 5 (full-screen mode)
Recent workload history	Option 6 (full-screen mode)
DB2 catalog information	RxD2 (RX option)

Quick Reference Card

MAINVIEW for DB2

How to Activate Requests

- To define requests for automatic startup (BLKDMRW member in BBPARM):
 - Summary Trace example

```
REQ=ATRAC THRDHIST TYPE=SUMMARY TITLE='THREAD HISTORY' STORAGE=4000K LOGTRAC=Y TRNUMDS=3 TRSWTIME=24:00 TRDSN='Mypfx. Trace. Dsn. V01'
```

Detail Trace example

```
REQ=ATRAC DETLABC DB2PLAN=ABC TYPE=SQL, SCAN, I O STORAGE=4000K WRAP=Y TI TLE=' I /O TRACE OF ABC' GROUPSQL=Y TRBUFF=5, TRSI ZE=800K
```

- Monitor example

```
REQ=BPUTL BPO WMAX=85 I =00: 01: 00 WLI M=99 LOG=ATWARN
```

See "SET Keyword Parameter Options" in Volume 2 of the MAINVIEW for DB2 User Guide for a complete description of all the keywords you can use.

- To define requests to check active thread exceptions ("runaway queries") or other background exception conditions (DMRBEX00 member in BBPARM):
 - TSO Exception example

```
MSG=DZ0630W, CPUT0T=1000, GPT0T=100000
```

See sample member DMRBEXBB in BBPARM or "Part 4 - Monitors" in Volume 2 of the *MAINVIEW for DB2 User Guide* for a complete list of all the background monitors.

To display the active background samplers, you can type **BG ON** from the Active Timer Requests application (Option 3).

- **To activate, modify, or purge individual traces,** use the Start Trace panels (ST option from Current Traces (Option 4)).
- To activate, modify, or purge individual monitors, use the Start Monitors panels (SM option from Active Timer Requests (Option 3)).
- To activate a block request with additional monitors or traces manually, type on any full-screen display:

```
SERV ===> SET
PARM ===> BLK=bl kmbrname
```

where bl kmbrname is BLKDMRW or a user-created block request member in BBPARM.

• To purge all existing requests from BLKDMRW manually, type on any full-screen display:

```
SERV ===> SET
PARM ===> PRG=BLKDMRWP
```

Chapter 2. Isolating DB2 Performance Problems

These scenarios teach you how to navigate easily through the MAINVIEW for DB2 views and displays and use the available facilities. They do not show you every area covered by the product or all of the displays.

In this practice session, you

- 1. Check status and activity of all DB2s to detect potential problem areas.
- 2. Analyze a single DB2 to study problem areas in more detail.
- 3. Use monitors to isolate specific resource- or workload-related problems.
- 4. Review critical problems, including those just identified by workload monitors.

See the *Using MAINVIEW* manual for a complete description of how to work in both windows mode and full-screen mode.

Note: This practice session takes approximately one hour to complete.

Enter MAINVIEW

If you are new to MAINVIEW, you should get a copy of the document *Quick Start with MAINVIEW* before starting. This consists of a few stapled pages that cover the basic things you need to know to use any MAINVIEW product. The first page has some blank lines that should be filled in with your startup options. See *Using MAINVIEW*, TD-906, for more detailed information.

Enter MAINVIEW by executing the MAINVIEW CLIST, selecting an ISPF panel option, or logging on to a VTAM session. Then go to Option 0 to specify your CASID, and, when this is done, return to the MAINVIEW Selection Menu, as shown in Figure 1.

Accessing MAINVIEW for DB2




Figure 1. MAINVIEW Selection Menu

You can enter any installed MAINVIEW product from this menu. Start by selecting Option 5 to access MAINVIEW for DB2.

Check DB2 Status and Activity

Traces

Views

Begin by accessing the MAINVIEW for DB2 Primary Option Menu, as shown in Figure 2.

```
PRIMARY OPTION MENU -----
                                                                               MAINVIEW for DB2 7.1.0
                      BMC Software
                     OPTION ===> V
                                                                                   DATE
                                                                                         -- 3/17/01
                                                                                        -- 13: 45: 08
                                                                                   TI ME
                         Managing DB2 Performance:
                                                                                   USERID -- CIR11
                                                                                   MODE -- ISPF 4.2
                           1 STATUS
                                            - DB2 Status (DB2ST)
Analyzers
                              ANALYZERS
                                             - Current Status/Activity Displays
Monitors
                                             - Early Warnings/Recent History (Active Timer Requests)
                           3
                              MONI TORS
                              TRACES
                                             - Current Application Traces
                           5
                              HISTORY TRACES - Historical Trace Data Sets
                           6
                                            - Recent Thread History
Thread History
                              GRAPH
                           7
                                             - DB2 I/O Analysis
                              I/0
                              BBI INFO
                                             - BBI Subsystem Information
                           V
                              VI EWS
                                             - Windows Mode (New Facilities)
                         DB2 administration:
DB2 Catalog
                           RX RxD2 FlexTools
                         General Services:
                           C CYCLE SETUP
                                           - Service Refresh Cycle Setup
DB2 Console
                           L LOG DISPLAY - Display Logs
                              MESSAGES
                                             Display Messages and Codes
                                             Current PF Key Assignments
                           K
                              KEYS
                                                                                   PF1/13: HELP
                              TUTORI AL
                                             Tutorials/News/Getting Started
                           X EXIT
                                            - Terminate
                                                                                   PF3/15: EXIT
```

Figure 2. MAINVIEW for DB2 Primary Option Menu

From here, you have direct access to all facilities provided by MAINVIEW for DB2. Most of the options shown here provide direct access to data displays and control panels for managing a single DB2 at a time. You can change the target DB2 directly on almost every screen. Most of these functions operate in full-screen mode.

However we are first going to investigate the capabilities of the windows-mode views, since they are specially designed to provide an overview of multiple DB2 subsystems at a time, as well as drill-down to details about any single DB2.

Point-and-shoot hyperlinks take you from one view to other displays with related information. Sometimes these displays are further windows-mode views; sometimes they are full-screen displays normally accessed through these menu options.

Check Status of All DB2s

To access windows mode and get acquainted with the views available for monitoring multiple DB2s at a time:

1. From the Primary Option Menu, select the **VIEWS** option.

```
OPTION ===> V
```

The DB2 SSI Easy Menu (EZDSSI) is displayed, as shown in Figure 3.

Window
Information
Line ==>

DB2 Overview




Figure 3. DB2 SSI Easy Menu (EZDSSI)

2. Look at the fourth line from the top.

This is the *window information line*. It shows the number of this window (since you may later have several windows open at once), the name of this view (EZDSSI), the current target context (ALL), date, time, and product (MVDB2).

This view is an example of an Easy Menu that provides hyperlinks to various other views.

Note: Options prefixed with a period take you directly to data, while options prefixed with a ">" take you to another menu.

This EZDSSI Easy Menu is designed to be used in Single System Image (SSI) mode to look at multiple target DB2s at one time.

- 3. There are two hyperlinks to other Easy Menus that can be used to check out DB2 status:
 - **Status Menu** provides options to select the many views that show complete DB2 statistics (EZDSTAT). EZDSTAT hyperlinks generally go to tabular views that show one row per DB2 with detail views accessible from there.
 - **Buffer Pools** provides options to show status and statistics for individual buffer pools (and group buffer pools).

Look at these menus but don't go further now. You can come back here later.

4. To check the status of all DB2s, put your cursor on the **Overview** hyperlink and press **Enter**.

This takes you to the STDB2 view, as shown in Figure 4, maintaining the default context of ALL, which includes all defined DB2s.

Check Status of All DB2s

COMMAND ===> CURR WIN ===> ALT WIN ===>	17MARO1	16: 41: 51			I NFORMATI	ON DIS	SPLAY				
>W1 =STDB2=======(ALL====*====) 17MAR01==16: 41: 51===MVDB2====D===3 DB2 Act Comm Getpg Lockout Total Dataset Dataset Dataset Dataset Getpg Target Thrd Rate Rate Excpt Warning Msg In-Use Open DBOGC 0 0.0	COMMAND	===>							SCROLL	===> CSR	
DB2	CURR WIN	===> 1		ALT WIN	===>						
Target Thrd Rate Rate Rate Excpt Warning Msg In-Use Open DBOGC 0 0 0 0 0 Connect Fail 0 DBOHC 0 0 0 0 0 Connect Fail 0 DB1GC 0 0 0 0 0 Connect Fail 0 DB1HC 2 0 0 1 0 0 GBL cont >2% 4 18 DB2GC 0 0 0 0 0 1 Connect Fail 0	>W1 =STDB2======(ALL=====*=====) 17MAR01==16: 41: 51====MVDB2====D===3										
DB0GC	DB2	Act	Comm	Getpg	Lockout	Total			Dataset	Dataset	G
DBOHC 0 0 0 0 0 0 connect Fail 0 DB1GC 0 0 0 0 0 0 connect Fail 0 DB1HC 2 0 0 1 0 0 GBL cont >2% 4 18 DB2GC 0 0 0 0 1 Connect Fail 0	Target	Thrd	Rate	Rate	Rate	Excpt	Warni ng	Msg	In-Use	0pen	
DB1GC 0 0.0 0.0 0.0 0 Connect Fail 0 DB1HC 2 0.0 0.1 0.0 0 GBL cont >2% 4 18 DB2GC 0 0.0 0.0 0.0 1 Connect Fail 0	DBOGC	0	0.0	0.0	0. 0	0	Connect	Fai l	0		
DB1HC 2 0.0 0.1 0.0 0 GBL cont >2% 4 18 DB2GC 0 0.0 0.0 0.0 1 Connect Fail 0	DBOHC	0	0.0	0.0	0. 0	0	Connect	Fai l	0		
DB2GC 0 0.0 0.0 0.0 1 Connect Fail 0	DB1GC	0	0.0	0.0	0. 0	0	Connect	Fai l	0		
22.40 0 0 0 0 0 0 1 comment rail	DB1HC	2	0.0	0. 1	0.0	0	GBL cont	>2%	4	18	
DD911C	DB2GC	0	0.0	0.0	0.0	1	Connect	Fai l	0		
DDZRC 5 U.U 11.U U.U U GBL CORT >2% 16 37	DB2HC	5	0.0	11.0	0.0	0	GBL cont	>2%	16	37	

Figure 4. DB2 Activity Overview (STDB2)

With this view, you can quickly gauge how well each of your DB2 subsystems is performing by reviewing and comparing the number of active threads, key activity rates, a total exception count, and the most critical warning condition that exists right now (if any). Notice the ">" sign before the W1 in the information line. This indicates that you can scroll right for more data.

Later you will see how you can move these fields around and set thresholds to customize the view to meet *your* monitoring needs exactly (or even create different views for different conditions).

5. Several of the column headers are highlighted, indicating that you can choose a row in that column. This hyperlinks to a view with more detail (related to that column) for the selected DB2.

If you see a warning message for one DB2, place the cursor on that message and press **Enter** to see a list of all the warning conditions that are tracked per DB2. If multiple conditions exist at the same time, only the most important is shown in STDB2, and the others are set to YES in this view. Press **PF3** to return to STDB2.

Note: You can do this hyperlink to see the list even if the warning message field is blank (all the conditions will be set to NO).

6. Hyperlink on the **DB2 Target** field for an active DB2 to see a detail status view.

You will return here later. Press PF3 to return to STDB2.

7. Hyperlink on the **Comm Rate** field for an active DB2 to see counts and rates of activity in that DB2, both for the current interval (1 to 15 minutes) and for the total session data since DB2 startup.

Interval and Session Counts

							-				
17MAR01 16: 37	: 54	INFOR	MATION DISE	PLAY			-				
COMMAND ===>						OLL ===> CS	R				
CURR WIN ===> 1 ALT WIN ===>											
>W1 =STDB2====STRATE==(ALL======DB2HC===)17MAR01==16:37:52====MVDB2====D====1											
	Interval	Sessi on	Interval	Sessi on	Interval	Sessi on	I				
	Qty	Qty	Rate	Rate	/Thread	/Thread					
Commits	16	52	0. 0	0. 0	2. 0	1. 1					
Thd Creates.	8	46	0. 0	0. 0							
Getpages	18431	30434	38. 8	1. 2	2303. 9	661. 6					
Page Updates	209	211	0.4	0.0	26. 1	4. 6					
Sync I/0	259	560	0. 5	0.0	32. 4	12. 2					
Prefetch I/O	2153	3502	4. 5	0. 1	269. 1	76. 1					
Write I/O	4	5	0. 0	0.0	0. 5	0. 1					
DatasetOpens	16	45	0. 0	0.0	2. 0	1. 0					
Lockouts	2	2	0. 0	0.0	0. 2	0. 0					
LockSuspends	21	51	0.0	0.0	2. 6	1. 1					
GBLLockCont.	36	924	0. 1	0. 0	4. 5	20. 1					
Clm/Drn Fls.	0	0	0.0	0.0	0.0	0. 0					
DML SQL	1196	1700	2. 5	0. 1	149. 5	37. 0					
StProcCalls.	0	0	0. 0	0.0	0. 0	0. 0					
StProcFails.	0	0	0. 0	0.0	0. 0	0. 0					
RID Fails	0	0	0. 0	0. 0	0. 0	0. 0					
EDM Loads	5	10	0. 0	0. 0	0. 6	0. 2					
EDM Fails	0	0	0. 0	0. 0	0. 0	0. 0					
Checkpoi nts.	0	1	0. 0	0. 0	0. 0	0. 0					
-											
Prll Groups.	0	0	0. 0	0. 0	0. 0	0. 0					
PrllFallback	0	0	0. 0	0. 0	0. 0	0. 0					

Figure 5. Activity Rates (STRATE)

Again, some of these fields are highlighted, indicating that hyperlinks will take you to even more detail.

8. Press **PF3** to return to STDB2.

Current Thread Activity

From the DB2 status overview (STDB2), you can access current thread information:

1. Hyperlink on **ACTV THRD** to view a list of all active threads in the selected DB2, as shown in Figure 6.

All Active Threads

```
17MARO1 11: 59: 34 ----- INFORMATION DISPLAY -----
COMMAND ===>
                                                       SCROLL ===> CSR
CURR WIN ===> 1
                 ALT WIN ===>
>W1 =THDACTV======DB2H====*===17MAR01==11: 59: 20====MVDB2====D===3
        DB2 Connect
                               El apsed
                                                   SOL.
                    CPU Time
Auth ID ID Name
                                 Ti me
                                           %CPU Stmts Warn Locks User
                                                  2 No
BOLHHH4 DB2H DB2CALL 00: 01: 22. 06 00: 08: 24. 48 2. 1
                                                              8 ACTI V
BOLLAA2 DB2H DB2CALL 00: 01: 07. 16 00: 05: 58. 88 0. 8
                                                23251 No
                                                              15 ACTIV
                                                2 No
BOLLAA2 DB2H DB2CALL 00: 00: 00. 00 00: 00: 02. 11
                                                              4 SWAPP
                                           0.0
DMRC
        DB2H DB2CALL 00: 00: 32. 12 05: 40: 25. 95
                                                    0 No
                                                               O BBI M
                                          0.0
```

Figure 6. All Active Threads for One DB2 (THDACTV)

- 2. Type **SORT D** on the COMMAND line, move your cursor to the **Elapsed Time** header, and press **Enter** to sort the threads by the length of time they have been active.
- 3. Hyperlink on one thread by placing your cursor in the **AUTH ID** column to see a detail display for that thread, as shown in Figure 7.

```
Detail User
Expand to
Locks Held =>
SQL Detail =>
```

Expand to SQL Detail =>

SQL Statement

```
BMC Software -----
                     DETAIL USER STATUS
SERV ==> DUSER
             INPUT 15: 01: 07 INTVL=> 3 LOG=> N TGT==> DB2G
PARM ==> BOLHHH4
                                 ROW 1 OF 80 SCROLL=> CSR
EXPAND: MON(USER), UTRAC, ST(START TRACE), LOCKE, EXPLAIN, PT, CICSE, CMRTASK
       ACCOUNTING: ENV, ELAPSED, SQLCOUNTS, BPOOL, LOCKS, PRLL, SPAS, DDF
CURRENT...... 11: 07: 13. 53 PLAN...... DSNESPRR TYPE............. ALLI ED
STATUS...... I N- DB2 COMMITS..... O ROLLBACKS....... 0
   ______
RUNTIME ANALYSIS IN DB2 IN APPL. TOTAL
                                      \%INDB2(=)
                                                 TOTAL(*)
 -----
                                    0 . . . 25. . . 50. . . 75. . 100%
ELAPSED TIME 00: 08: 23 718 ms 00: 08: 24 \mid =====* \mid CPU TIME 00: 01: 22 123 ms 00: 01: 22 \mid ===
CPU TIME 00: 01: 22
DB2 WAIT TIME 20 s
- - - - - ACTI VI TY - - - - -
                          - - - - KEY INDICATORS - - - - -
GETPAGES......416, 803
SYNC READS (PRLL=00) .....147
PREFETCH PAGES READ......1, 051
UPDATES/COMMI T. . . . . . . . . . . . . . . 0. 0
BFR HIT RATIOS: . . . VP=100%, HP=100%
193
                          STATEMENT TYPE: OPEN
STATEMENT #:
                    CPU TIME: 1,897 ms ELAPSED TIME: 00:01:06
ACTIVE IN DB2
Package/DBRM: DSNESM68 (DYNAMIC)
                             PLAN ISOLATION LEVEL: RR
PROCEDURE/UDF/TRI GGER: DSN8SPAS_TEST
SELECT * FROM LONG_SQL ;
```

Figure 7. Detail User Status Display (DUSER)—Base Section

Check DB2 Status and Activity

This display shows all available accounting detail information about that thread. The most critical data is summarized in the base section, including key indicators of failures or potential problems. You can scroll down, use the expand buttons, or point-and-shoot to view complete detail data. Also, the DB2 thread cancel command can be invoked with a CANCEL parameter if you have the proper authorization.

4. The full text of the current SQL statement being executed is available near the bottom of this base section.

If your window size is too small to show the full text, position the cursor on the first text line and scroll down with **PF8**.

Notice that this section also includes the current package/DBRM name and the time this SQL statement has been active.

- 5. Tab to the **SQLCOUNTS** button or to the **TOTAL SQL** line and press **Enter** to view a breakdown of all SQL executed by this thread.
- 6. Press **PF3** once to return to the DUSER base section.
- 7. If this is an active IMS or CICS thread and if MAINVIEW for IMS or MAINVIEW for CICS is installed, the detail display will include an expand button to expand directly to that product:
 - MAINVIEW for CICS: TASKXPND display for this CICS transaction
 - MAINVIEW for IMS: DREGN display for the region processing this IMS transaction Press **PF3** once to return to DUSER.
- 8. There are many other sections of detail data with which you will get acquainted over time. For example, if you are concerned about locking, you could choose the **LOCKE** expand button to see all the locks held (or waited on!) by this thread and any threads in contention with it.
- 9. Press **PF3** several times to return to EZDSSI.

Exceptions Overview

Another way to check for exception conditions in any of your DB2s quickly is to choose the **Exceptions** hyperlink on EZDSSI to bring up the view STEXC, as shown in Figure 8.

Exception Conditions




Figure 8. Exception Conditions (STEXC)

This view identifies immediately whether or not any exceptions have been detected, and shows what kind they are. Hyperlinks lead to additional details.

Warning Monitors show conditions that have been detected by timer-driven sampling monitors defined with warning thresholds. Typically, a predefined group of monitors is started automatically and it is always active. A later section provides more information on monitors.

System Exceptions are conditions that are detected by a background sampler and are not governed by a threshold; for example, a problem with log archiving.

User Exceptions are thread-related conditions detected by a background sampler. Threshold conditions can be defined per attach type; for example, IMS, CICS, or batch.

The first three types generate warning messages that can be viewed while active, tracked historically in the journal log, or fed into an automated operator product like MAINVIEW AutoOPERATOR.

Warning Msg shows the most important of several conditions that are checked per interval, and on request, as part of the total DB2 status and statistics data collection for windows-mode views. These conditions may also be identified by one of the other exception samplers.

- 1. If you have a non-zero value for any of these counts, follow the hyperlinks to see further details.
- 2. When finished, press PF3 as needed to return to EZDSSI.

Thread Activity for Multiple DB2s

From EZDSSI, you can choose hyperlinks to view thread activity across multiple DB2s:

- 1. Hyperlink on **Current Threads** to see all active threads, identified by the DB2 they are running in.
- 2. Hyperlink on **DB2 Summary** to see a summary of threads for each DB2; then hyperlink on **one row** to view a list of threads for just that DB2.

Analyze One DB2

From EZDSSI, choose the **Easy Menu** hyperlink to access an Easy Menu designed to analyze one DB2 at a time, EZDB2, as shown in Figure 9. This selects one DB2 from the context of ALL.

17MARO1 12: 41: 15 ----- INFORMATION DISPLAY -----SCROLL ===> CSR CURR WI N ===> 1 ALT WI N ===> W1 =EZDB2======DB2HC===*===17MAR01==12: 41: 14====MVDB2====D===1 DB2 Easy Menu DB2 Target ---> DB2HC Status Threads +----- Current Threads Lockouts Monitors Tools And Menus

Events In Warning Set Target Context

Resource Summary Sy Area DB2 Catalog/Explain

Connection Summary Active SSI Easy Menu Blocker/Waiter Summary . Workload Objectives > DBA Easy Menu > Fast Menu Page Sets > MAIN Menu . Page Set Status > Tuni ng Wi zards . Volume I/O Summary . Return... > Page Set Menu

Figure 9. DB2 Easy Menu (EZDB2)

To select the target DB2 you want to analyze:

1. Hyperlink on **Set Target Context** to see a list of targets; then place your cursor in the **Target** column and press **Enter** to hyperlink to a different target.

Note: If you already know the DB2 target you want, simply type **CON target** on the COMMAND line.

2. Notice in the **Tools And Menus** section, there are hyperlinks to RxD2 (DB2 Catalog/Explain) as well as several other Easy Menus.

One DB2

Check DB2 Status

To check the status of the target DB2:

1. Hyperlink on **Overview**.

This takes you to the STDB2 view, as shown in Figure 4 on page 9, but only the one DB2 is displayed.

2. Now you may want to review recent history.

Type **TIME** * * **2H** to see the last 2 hours by 15-minute intervals. Type **INCLUDE TIME** to see the times (the Intvl Time column is added to the view), as shown in Figure 10.

Review History

Figure 10. DB2 Activity Overview (STDB2)

You can hyperlink on a time period for further analysis if desired. (Don't do it now though.)

- 3. Reset to current time with **TIME** * * **1I** and then **EXCLUDE TIME**.
- 4. Hyperlink on **DB2 Target** to see a detail status view, as shown in Figure 11.

Detail Status View

17MARO1 16: 58: 31 INFORMATION DISPLAY										
COMMAND ===>					SCROLL ===>	CSR				
CURR WIN ===> 1 ALT WIN ===>										
>W1 =STDB2====S		32HC====*==	=====17MAR01	1==16: 57: 54===	==MVDB2====D=	===1				
> EZ Menu	. Sessi on									
	Connect	Acti ve	In DB2	Queued	Suspended	CPU%				
TS0	1	1	0	0	0	0. 0				
Batch	4	4	2	0	1	32. 0				
- CAF	4	4	2	0	1	32. 0				
- Utility	0	0	0	0	0	0. 0				
Cerricy	· ·	Ü	Ü	· ·	· ·	0. 0				
I MS	0	0	0	0	0	0. 0				
CI CS	0	0	0	0	0	0. 0				
DBAT	0	0	0	0	0	0. 0				
SPAS	9	0	0	0	0	0. 0				
RRSAF	0	0	0	0	0	0. 0				
*Total *	14	5	2	0	1	32. 0				
		0 50. 10	00	0 50. 100						
GBL cont >2%	EDM Pool		Total CPU%	6						
BP Rates:	Getpage	4. 7	Reads	0	Writes	0. 0				
Locki ng:	Suspend	0	Deadl ocks	0	Ti meouts	0				
Exceptions:	Monitor	0	System	0	User	0				
Data Sets:.	0pen	63	Open HWM	63	In-use	4				
Parallel:	Maxi mum	0	Groups	0	Fal l back	0				
STOPROCS:	Calls	0	Abends	0	Ti meouts	0				
Group BP:	Reads	2	Writes	2	Fai l ures	2				
Pagi ng:	DB2	0.0	System	0. 0						
DB2 Start:.	Date	17MAR01	Ti me	09: 19: 46						

Figure 11. DB2 Status Detail—Interval (STDB2D)

This shows an overview of current thread activity per attach type as well as key indicators of recent performance.

- 5. Use the **.Session** hyperlink at the top of the view to see totals since DB2 startup instead of current interval values in the key indicator fields.
- 6. The **EZ Menu** option takes you to EZDSTATD.

This Easy Menu is very similar to the DB2 Status Easy Menu, EZDSTAT, that you saw earlier, but the hyperlinks here take you directly to all the detailed statistics views for this DB2.

7. Hyperlink on **SQL Counts** to see STSQLD as an example of these detailed statistics views, as shown in Figure 12.

17MARO1 17: 01: 51 ----- INFORMATION DISPLAY -----COMMAND ===> SCROLL ===> CSR CURR WIN ===>1ALT WIN ===> W1 = STDB2====STSQLD===DB2HC====*=====17MAR01==16: 57: 54====MVDB2====D===1 Interval Session Data Manipulation Language 0 0 SELECT.... 0 0 2 UPDATE.... 6 0 0 0 0 PREPARE..... 12 205 10 199 FETCH..... 150 46998 9 197 Data Definition Language.. CREATE TABLE..... 0 0 $I\, NDEX.\, \dots \dots \dots$ 0 0

Figure 12. SQL Counts Detail (STSQLD)

8. Press **PF3** to return to EZDSTATD.

You may want to browse a few other detail views.

- 9. Press **PF3** to return to STDB2D.
- 10. Hyperlink on **TSO** to see a tabular view of current TSO users.
- 11. We have stepped through several status views now. However, some information is not available in windows mode. Examples are information about CICS connections, DB2 logging, DSNZPARM values, and so forth.

To access these displays, simply press **PF3** to return to the Primary Option Menu, or you can use one of the following quick paths:

- From EZDB2, choose the Fast Menu to get a menu of hyperlinks into full-screen mode.
- Use the transfer command at any point to access the full-screen DB2 Status display DB2ST. This is similar to STDB2D, but it provides point-and-shoot to most full-screen displays, such as CICSC (to see CICS connections), ZPARM, and so forth.

TRAN target DB2; EX DB2ST

You can also use the transfer command to access other MAINVIEW products.

Detailed View

Buffer Pools

To analyze buffer pools for the target DB2:

1. From EZDB2, hyperlink on **Buffer Pools** to see a list of all defined pools with allocated space, utilization, and getpage rates, as shown in Figure 13.

All Defined Pools

17MARO1 17: 04: 18 INFORMATION DISPLAY									
COMMAND	===>							S	SCROLL ===> CSR
CURR WI	N ===> 1		ALT WI	N ===>					
W1 = BF	RPL=====		-DB2HC=	===*===	====17	MARO1==	17: 04: 1	8====N	NDB2====9
Pool	DB2	Vpool	Vpool	Hpool	Hpool	Getpg	Get-	%	% Active
Name	Target	Si ze	Alloc	Si ze	Alloc	/sec	pages	Actv	0 50 100
BPO	DB2HC	200	200	0		143. 2	37236	0	
BP1	DB2HC	25		0		0.0	0	0	
BP2	DB2HC	25		30		0.0	0	0	
BP4	DB2HC	21		0		0.0	0	0	
BP5	DB2HC	30		0		0.0	0	0	
BP9	DB2HC	20		0		0.0	0	0	
BP11	DB2HC	400		0		0.0	0	0	
BP32K	DB2HC	20		0		0.0	0	0	
BP32K9	DB2HC	20		0		0.0	0	0	

Figure 13. Buffer Pool Statistics—SSI (BFRPL)

2. Hyperlink on **Pool Name** to see all status and statistics for one pool.

Both interval and session counts are shown, as shown in Figure 14.

Statistics for One Pool

17MARO1 17: 05: 05 INFO COMMAND ===> CURR WIN ===> 1 ALT WIN ===:		SPLAY	SCROLL ===> CSR
CURR WIN ===> 1 ALT WIN ====: W1 =BFRPL====BFRPLD===DB2HC====*=:		AR01==17: 0	4: 18====MVDB2====D====1
Pool Name	BP0		
VP Si ze	200		
Hi perpool Si ze	0		
Virtual Pool Sequential Threshold	80		
Hiperpool Sequential Threshold	80		
Deferred Write Threshold	50		
Vertical Write Threshold	10		
Castout Attribute Y/N	Y		
Parallel Sequential Threshold	50		
Assisting Parallel Threshold	0		
	Interval	Sessi on	
Virtual Pool Allocation			
Buffers Allocated		200	
Current Active Buffers		1	
Expansi ons/contracti ons	0	0	
No Buffer - Pool Full	0	0	
Expansi on Fail	0	0	
Hiperpool Allocation			
Expanded Storage Buffers		0	
Buffers Allocated		0	
Expansi ons/Contracti ons	0	0	
Virtual Pool Read Statistics			
Getpages	37236	135607	
Sequential Getpages	36910	128765	
Sync I / 0	104	1657	
Sequential Sync I/0	0	289	

Figure 14. Local Buffer Pool Statistics Detail (BFRPLD)

- 3. Scroll down with PF8 to see all the data. Press PF3 to return to BFRPL.
- 4. Hyperlink on **Getpg/sec** to see current hit ratios per pool (BFRPLH); then hyperlink on **Pool Name** to see both current and session ratios (BFRPLHD) for one pool, as shown in Figure 15.

17MAR01 17: 07: 12 ------ INFORMATION DISPLAY -----COMMAND ===> SCROLL ===> CSR CURR WIN ===>1ALT WIN ===> W1 =BFRPL===BFRPLHD==DB2HC====*=====17MAR01==17: 04: 18====MVDB2====D===1 Pool Name..... BP0 Interval Session Hit Ratios..... 17.51 VPOOL Hit Ratio % with P/F... 18. 55 VPOOL Hit Ratio % without P/F 92.64 81.70 GBP Hit Ratio %..... 0.00 18. 92 Activity per Second..... Getpages..... 143. 20 4.87 Page Updates..... 29. 78 0.61 Sync I/0..... 0.40 0.06 Prefetch I/0.... 15. 51 0.51 Write I/0..... 0.80 0.02 Data Set Opens..... 0.00 0.00

Figure 15. Buffer Pool Rates Detail (BFRPLHD)

5. Press **PF3** to return to EZDB2.

Group buffer pools are discussed later in the data sharing section (see "Tune Group Buffer Pools" on page 54).

Hit Ratios

Lock Contention Analysis

Although locking problems must usually be resolved at the application level, the first indication of problems—and the simplest identification of the applications and resources involved—can best be seen at the system level. To use the options in the Lockouts section of EZDB2 to look at locking problems in one DB2 (without data sharing):

1. If you aren't sure whether or not you are having much lock contention, you may want to review the lockout and suspension counts and rates first in the STRATE view (hyperlink on **Activity Rates**).

A certain number of lock suspensions (and even an occasional timeout or deadlock) is to be expected in an active DB2 system. More frequent lockout conditions (either timeouts or deadlocks) may be a cause for concern, since the SQL statements involved are terminated.

2. You can hyperlink to see a list of the last 100 timeouts and deadlocks either from the **Lockouts** field in STRATE, or from **Lockout Events** on EZDB2.

Both go to the view LKEVENT, as shown in Figure 16.

Timeouts and Deadlocks

17MARO1 17: 20: 11 INFORMATION DISPLAY									
COMMAND ===>						SCROLL ===>	CSR		
CURR WIN ===> 1	AL'	Γ WI N ===	>						
>W1 =LKEVENT====	=====DB	2HC====*=	=====17	MARO1==17:	20: 10==	===MVDB2====D=	===5		
Date / Time	Lockout	Victim	Victim	Vi cti m	Victim	Victim	Nr.		
	Type	Pl an	AuthI D	Connect	CType	Corr ID	Res.		
17MAR- 16: 58: 56	DEADLOCK	AUDI T	BBLLAT5	TS0	TS0	BBLLAT5	2		
17MAR- 16: 58: 45	TI MEOUT	PAYROLL	DMRDLK3	BATCH	BATCH	DMRDLK3	1		
17MAR- 16: 42: 34	TI MEOUT	PAYROLL	DMRTM03	BATCH	BATCH	DMRTM03	1		
17MAR- 16: 37: 33	DEADLOCK	AUDI T	BBLLAT5	TS0	TS0	BBLLAT5	2		
17MAR- 16: 36: 53	TI MEOUT	RXDB2	AXCNM1 1	DB2CALL	CAF	AXCNM11	1		

Figure 16. Lockout Events (LKEVENT)

This view shows a chronological list of up to 100 lockout events that have occurred since DB2 startup, sorted with the most current at the top of the screen.

- 3. Type **SORT** and tab to the **Victim Plan** column to sort these lockout events by plan name to identify the applications for which SQL requests were terminated.
- 4. Hyperlink on the **Date/Time** field for an event (preferably a deadlock that involves multiple resources).

The first view shows the resources involved and holder (blocker) and waiter plans.

- 5. Scroll right to see additional details for both resources at once, or hyperlink on the **Res Seq** field to see all the available details for this conflict.
- 6. Press PF3 to return to EZDB2.

Although you may have analyzed lockout conditions one at a time like this before, the windows-mode views provide additional analysis capabilities. They are available through the other three hyperlinks in the lockouts section of EZDB2.

7. Hyperlink on **Resource Summary** to do an analysis of the resources involved in timeouts or deadlocks, as shown in Figure 17.

Resources Involved

```
17MARO1 17: 21: 09 ----- I NFORMATI ON DI SPLAY -----
COMMAND ===>
                                             SCROLL ===> CSR
CURR WIN ===> 1
              ALT WIN ===>
>W1 =LKRESZ======DB2HC===*=====17MAR01==17: 21: 09====MVDB2====D===2
--Resource Name-- Total
                         % Total
                        0...50..100 PAGE ROW INDEX Conflicts
Database Object Conflicts
0
                                             0
                                                       2
                   2 28.6 ***
DSN8D51A DSN8S51P
                                      0
                                          2
                                               0
                                                       2
```

Figure 17. Lockout Resource Summary (LKRESZ)

The first view, LKRESZ, summarizes all conflicts by resource name, usually database and table space. Note that a deadlock with three resources and participants will result in three conflicts, not one, for the purposes of this analysis. With this view, you can easily identify those table spaces involved in the most contention.

8. Hyperlink on a **resource name** showing one or more conflicts to see a breakdown of these conflicts by specific resource, down to a page or row level (LKRESNRZ).

With this view, hot spots in your tables are immediately visible, as shown in Figure 18.

See Hot Spots in Tables

Figure 18. Lockout Resource Number Summary (LKRESNRZ)

9. Hyperlink on either the **resource name** or the **resource number** to view a list of each lockout event that involved this resource (LKRESD), as shown in Figure 19.

The events are initially sorted in descending sequence by time, but the SORT command can be used to sort by any column. (If you have forgotten how, type **HELP SORT** on the COMMAND line.) This allows you to identify the applications (blocker planname, waiter planname) and users (blocker/waiter Corr ID, Connection, Victim Auth ID) involved quickly.

Each Event for This Resource

```
17MARO1 17: 24: 34 ----- I NFORMATI ON DI SPLAY ------
COMMAND ===>
CURR WIN ===> 1
                    ALT WIN ===>
>W1 =LKRESZ===LKRESD===DB2HC====*=====17MAR01==17: 24: 34====MVDB2====D===5
 --Resource Name-- Resource Resource Time Lockout Blocker Waiter
Database Object Number
                           Туре ----- Туре
                                                     PlanName PlanName Con
DSN8D51A DSN8S51E 0000001200 DATAPAGE 16: 58: 56 DEADLOCK PAYROLL AUDIT
DSN8D51A DSN8S51E 0000001200 DATAPAGE 16: 58: 45 TI MEOUT AUDIT
                                                              PAYROLL
DSN8D51A DSN8S51E 0000001200 DATAPAGE 16: 42: 34 TI MEOUT AUDIT
                                                              PAYROLL
DSN8D51A DSN8S51E 0000001200 DATAPAGE 16: 37: 33 DEADLOCK PAYROLL AUDIT
                                                                      Yes
DSN8D51A DSN8S51E 0000001200 DATAPAGE 16: 36: 53 TIMEOUT RXDB2
                                                              RXDB2
```

Figure 19. Lockout Resource Conflict Detail (LKRESD)

Although the solution to locking problems may involve application or table redesign, at least you now know where the problems lie.

10. Press **PF3** until you return to EZDB2 and hyperlink on **Connection Summary** if you suspect that the problem may lie in application scheduling, where applications with incompatible lock usage are running concurrently, as shown in Figure 20.

Application Scheduling Problems

17MARO1									
CURR WIN ===> 1 ALT WIN ===>									
W1 =LKCC)NZ=====	====DB2HC	*	====17MAR01==17:	38: 41	====MVDB2====1			
DB2	Vi cti m	Victim	Blocker	Timeouts Deadl	ocks	% Lockouts			
Target	ConnType	Connect	Connect			0 50 100			
DB2HC	TS0	TS0	BATCH	0	2	40. 0 *****			
DB2HC	BATCH	BATCH	TS0	2	0	40. 0 *****			
DB2HC	CAF	DB2CALL	CAF	1	0	20. 0 ***			

Figure 20. Lockout Connection Summary (LKCONZ)

The view LKCONZ summarizes the conflict data to identify, for example, whether batch jobs or utilities are blocking critical CICS or IMS transactions. As in the resource summaries, hyperlinks lead to lists of the exact events with time stamps, so that the critical time periods can be seen at a glance.

11. Press **PF3** until you return to EZDB2 and hyperlink on **Blocker/Waiter Summary** in order to identify incompatible applications that are frequently blocking each other, as shown in Figure 21.

Incompatible Applications

17MARO1 17 COMMAND ==			- INFORMAT	I ON DI	SPLAY		LL ===> CSR
CURR WIN ==	==> 1	ALT V	VI N ===>				
>W1 =LKBWZ=		====DB2H0	:====*====	===171	MAR01==17: 40: 24	====MVDB	2===D====1
Blocker V	Waiter	Ti meout	Deadl ock		% Conflicts	Gl obal	Parti ci pant
PlanName I	Pl anName	I nvol v.	Invovl.		0 50 100	Confl.	-Only Count
AUDI T I	PAYROLL	2	0	40.0	****	0	0
PAYROLL A	AUDI T	0	2	40.0	****	0	0
RXDB2 I	RXDB2	1	0	20.0	***	0	0

Figure 21. Lockout Blocker/Waiter Summary (LKBWZ)

The view LKBWZ summarizes the conflict data by blocker and waiter plans, so that you can quickly see which applications are causing the most conflicts. The hyperlinks again show all of the lockout events where the selected plan was involved.

- 12. Press **PF3** until you return to EZDB2.
- 13. To see current contention, hyperlink to the **Fast Menu** (on the right under Tools And Menus).

In the Lock Activity section, there are two valuable options:

- Hyperlink on **User Contention** to see a list of active threads with lock counts (LOCKU). Holding and waiting threads in current conflicts are identified.
- Hyperlink on DB/TS Contention to see a list of resources in contention, showing the lock owner and waiters (LOCKD).

From both of these displays, you can hyperlink on one conflict to see additional details. The LOCKE display shows a thread with all locked resources and identifies waiter threads per resource.

Note: LOCKU is also accessible through hyperlinks in several thread views (THDxxx).

Page Set Status and I/O Analysis

The tuning of physical I/O and page set usage in the buffer pools is a critical success factor in DB2. DB2 itself uses many techniques to reduce or defer I/O, but the setup, from DASD volumes to buffer pool allocation and thresholds, all plays a part. To use the options in the Page Sets section of EZDB2 and the Page Set Easy Menu itself to look at data object issues with the focus still on a single DB2:

1. The first thing to review is simply the status of all open page sets. Hyperlink on **Page Set Status** to see a list sorted by object name (database, table space, partition), as shown in Figure 22.

Sort by Object Name

17MARO1 : COMMAND =	16: 11: 08 -			1 1/1	r UKWA I	ION DISFI	LAI			ROLL =		SP
CURR WIN :			ALT WI	N					30	KULL =	==> (JON
	> 1 AT======					17MAR	1116	11.6	18M	/DR2		-77
	ge Set					1 / WAIC	% %	. 11. \	First	Defr Defr		GBP
,	Obj ect			Tv	Users	Si ze(K)		EXT			ERR	
	DSN4K01			TS	0				BAB310	0	N	БСР
DSNDB01			BPOO	TS			100. 0		BAB310	1	N	
DSNDB01	DSNLLX01	001	BP00	ΙX					BAB310	0	N	
DSNDB01	DSNLLX02	001	BP00	ΙX	0	240	80. 0	1	BAB312	0	N	
DSNDB01	DSNLUX01	001	BP00	ΙX	0	48	33. 3	1	BAB320	0	N	
DSNDB01	DSNLUX02	001	BP00	ΙX	0	48	33. 3	1	BAB320	0	N	
DSNDB01	DSNSCT02	001	BP00	ΙX	0	144	11. 1	1	BAB310	0	N	
DSNDB01	DSNSPT01	001	BP00	ΙX	0	240	40.0	1	BAB312	0	N	
DSNDB01	DSNSPT02	001	BP00	ΙX	0	432	44. 4	1	BAB325	0	N	
DSNDB01	SCT02	001	BP00	TS	0	10080	14. 3	1	BAB310	1	N	
DSNDB01	SPT01	001	BP00	TS	0	5760	25. 0	1	BAB312	1	N	
DSNDB01	SYSLGRNX	001	BP00	TS	0	1440	100.0	1	BAB310	1	N	
DSNDB01	SYSUTI LX	001	BP00	TS	0	1440	100.0	1	BAB320	1	N	
DSNDB06	DSNADH01	001	BP00	ΙX	0	48	33. 3	1	BAB312	0	N	
DSNDB06	DSNAGH01	001	BP00	ΙX	0	96	16. 7	1	BAB314	0	N	
DSNDB06	DSNAPH01	001	BP00	ΙX	0	96	16. 7	1	BAB310	0	N	
DSNDB06	DSNATX01	001	BP00	ΙX	0	144	11. 1	1	BAB312	0	N	
DSNDB06	DSNATX02	001	BP00	ΙX	0	480	20.0	1	BAB312	0	N	
DSNDB06	DSNATX03	001	BP00	ΙX	0	432	22. 2	1	BAB312	0	N	
DSNDB06	DSNAUH01	001	BP00	ΙX	0	96	16. 7	1	BAB310	0	N	
DSNDB06	DSNDCX01	001	BP00	ΙX	0	2160	66. 7	1	BAB312	0	N	
DSNDB06	DSNDDH01	001	BP00	ΙX	0	48	33. 3	1	BAB310	0	N	
DSNDB06	DSNDDX02	001	BP00	ΙX	0	48	33. 3	1	BAB310	0	N	
DSNDB06	DSNDKX01	001	BP00	ΙX	0	192	50. 0	1	BAB318	0	N	
DSNDB06	DSNDLX01	001	BP00	ΙX	0	48	33. 3	1	BAB312	0	N	
DSNDB06	DSNDPX01	001	BP00	ΙX	0	96	100.0	1	BAB310	0	N	

Figure 22. Page Set Status (PSSTAT)

2. Sort on the **EXT** column to identify the data sets with the highest number of extents (a potential performance impact). Type **SORT D** and tab to the **EXT** column.

3. If you want to limit the view by selecting only certain page sets, one simple way is to use the WHERE command. It works very much like the SQL WHERE clause. First choose one (or more) column you want to filter the view on. Place the cursor in that column header and press PF1 to view the field help. Within the help, the element name is identified.

Now type **WHERE** on the COMMAND line. Under Where Condition, type the filters you want in effect.

For example, to show only those data sets with several extents, type

$I0_EXT > 5$

Press **PF3** to return to PSSTAT with the WHERE clause in effect. You can check the filters in effect in any view with the SHOWFILT command.

Note: Help for any command is available by typing **HELP commandname** on the COMMAND line.

As another example of filtering, to see only catalog tables, type

$IO_DBTSP = DSNDBO6*$

- 4. Hyperlink on the **Page Set** field to see complete details about the selected page set, including size, volume, buffer pool cache data, and detailed I/O counts and elapsed wait times. You may need to scroll down with **PF8** to see all the data.
- 5. Press **PF3** to return to PSSTAT.

Hyperlink on the **Users** column to see the threads currently accessing this page set. Or hyperlink on the **ERR** column to see if a restricted status is in effect for this table space.

- 6. Press **PF3** to return to EZDB2.
- 7. One of the most important issues to check periodically is data set placement and volume I/O response times.

Hyperlink on **Volume I/O Summary** to see the volumes in use for DB2 databases, as shown in Figure 23.

COMMAND ===> CURR WIN ===> 1	ATT					
CURR WIN $===>1$	A T OT				SCROLL	===> CSR
001111> 1	ALT	WI N ==	==>			
>W1 =PSV0LSZ======	====DB2	H=====	*====	====17MARO	1==11: 21: 48====MVDB2==	=====11
DB2	Nr.	Sync	I/0	Sync Max	Sync Avg	Async
Volume Target	PSs	I/0s	%	I/O Wait	I/O Wait 02040	I/0s
BAB309 DB2H	1	9	2.0	35	19 *****	1
BAB310 DB2H	16	141	31.0	325	24 *******	15
BAB312 DB2H	21	144	31.6	175	24 *******	43
BAB314 DB2H	5	25	5. 5	667	41 *******+	12
BAB316 DB2H	4	14	3. 1	38	14 ****	0
BAB318 DB2H	9	50	11.0	73	22 *****	21
BAB319 DB2H	1	2	0.4	31	17 *****	0
BAB320 DB2H	5	24	5. 3	51	19 *****	6
BAB321 DB2H	1	3	0. 7	32	22 *****	0
BAB325 DB2H	13	40	8.8	47	20 *****	7
BAB330 DB2H	1	3	0. 7	40	20 *****	1

Figure 23. Volume I/O Summary—Session (PSVOLSZ)

8. Type **SORT D** and tab to **Sync Avg I/O Wait** to sort the volumes with the highest average delays to the top.

Volumes In Use 9. These values are based on activity since DB2 startup.

To see a 2-hour summary of activity for one volume broken down into 15-minute intervals, hyperlink on **Sync I/Os**.

Press PF3 to return.

10. Hyperlink on a **volume** to see a list of all page sets on that volume.

You may want to scroll to the right to see the asynchronous I/Os made for prefetch, since these I/Os have different access characteristics and delay times than do synchronous I/Os.

11. Press **PF3** until you return to EZDB2 and hyperlink on the **Page Set Menu** option to go to EZDPS.

Hyperlink on any of the **I/O by Page Set** options to look at I/O counts and wait times per page set.

- Sort on the Avg I/O Wait column to identify the highest average delays that can point out DASD response time problems.
- Sort on Max I/O Wait to help identify occasional contention problems that are masked in the averages.

Note: However, be aware that the maximum is since DB2 startup, not per interval. This does reduce its usefulness.

12. Press **PF3** until you return to EZDPS and hyperlink on **Cache Statistics** to analyze page usage in the buffer pools and hiperpools by page set, as shown in Figure 24.

Cache Statistics

COMMAND =	==>						SCRO	LL ===>	CSR
CURR WIN =	==> 1		ALT WIN	===>					
					==17MARO1	==16: 18: 48=	===MVDB	2=====	==77
Pag	e Set		Bfrpl	VP	VP	VP	VP	VPTot	VPTot
Database	0bj ect	Prt	I D	Current	Maxi mum	Changed Ma	x Chng	% All	%BP
DB2HWORK	DSN4K01	001	BP00	0	2	0	2	0.0	0.0
DSNDB01	DBD01	001	BP00	7	23	0	6	4. 0	3. 5
DSNDB01	DSNLLX01	001	BP00	9	10	0	6	5. 2	4. 5
DSNDB01				3	8	0	6	1. 7	
DSNDB01	DSNLUX01	001	BP00	3	4	0	2	1. 7	1.5
	DSNLUX02			2	4	0	2	1. 2	1.0
	DSNSCT02			0	3	0	1		0.0
	DSNSPT01			0	3	0	1	0.0	0.0
	DSNSPT02			0	4	0	1	0.0	0.0
	SCT02			1	5	0	3	0.6	0. 5
DSNDB01	SPT01	001	BP00	1	5	0	3	0.6	0. 5
DSNDB01	SYSLGRNX	001	BP00	8	13	0	7	4.6	4.0
	SYSUTI LX			3	12	0	5	1. 7	1.5
	DSNADH01			2	3	0	0	1. 2	1.0
DSNDB06				2	3	0	0	1. 2	1.0
DSNDB06				0	3	0	0	0.0	0.0
	DSNATX01			2	3	0	2	1. 2	1.0
	DSNATX02			6	6	0	2	3. 5	3. 0
DSNDB06				3	4	0	2	1. 7	1. 5
DSNDB06				2	3	0	0	1. 2	1.0
	DSNDCX01			7	7	0	4	4. 0	3. 5
	DSNDDH01			2	3	0	0	1. 2	1.0
	DSNDDX02			0	3	0	0	0.0	0.0
	DSNDKX01			2	3	0	1	1. 2	1.0
	DSNDLX01			2	3	0	1	1. 2	1.0
DSNDB06	DSNDPX01	001	BP00	2	3	0	1	1. 2	1.0

Figure 24. Page Set Cache (PSCACHE)

You may want to sort on the **VP Current** column (descending) to sort those with the highest current storage usage to the top. The VP Changed and VP Max Chng columns identify those page sets with update activity.

13. Press **PF3** until you return to EZDPS and hyperlink on **Summary by Buffer Pool** for assistance in balancing table space allocations to the proper buffer pools, as shown in Figure 25.

Balance Table Space Allocations

COMMAND	001 16: 21: 0 ===> N ===> 1				ON DISPLAY			===> CSR
					17MAR2001-	-16: 21: 0	1MVDR2	====D====1
	DB2				HP		VP Max	
ID	Target				Current			U
BP00	DB2H	77	173	U	0	1341	23	15
BP02	DB2H	23	12	3	0	522	84	8

Figure 25. Buffer Pool Page Set Summary—Session (PSBPSZ)

The view PSBPSZ gives you a quick overview of how all the buffer pools are being used.

14. Hyperlink on Bfrpl ID to see a list of all page sets allocated to that pool (PSBPS). Sort on the VP Current column (descending) to sort those with the highest current storage usage to the top.

The VP Changed and VP Max Chng columns identify those page sets with update activity.

- 15. Press **PF3** until you return to PSBPSZ. Hyperlink on **VP Current** for a 2-hour history.
- 16. Press **PF3** until you return to EZDB2.

Use Monitors to Isolate Problems

Monitors sample key measurements over time and save short-term history. When thresholds are specified, the measured values are compared and automatic warnings generated.

A default set of monitors defined in BBPARM member BLKDMRW is automatically started. This set can be tailored for each DB2 system with different monitors or different thresholds.

To view the active monitors:

1. From the Primary Option Menu, select the MONITORS option.

```
OPTION ===> 3 (Active Timer Requests)
```

All *active* monitors are listed here. The current measurement values are shown and plotted compared to the thresholds. The W in the middle marks the warning threshold values. All monitors with acceptable values remain on the left side of the W. Those in warning status extend to the right and are highlighted, as shown in Figure 26.

```
BMC Software ----- ACTIVE TIMER REQUESTS -----
                                                               PERFORMANCE MGMT
                                                               TGT ===> DB2G
COMMAND ===>
                                                               TI ME -- 10: 52: 10
                                    INPUT
                                             INTVL ==> 3
COMMANDS: SM (START MONITORS), SORT, AREA, X ON | OFF, DM (DMON), DW (DWARN)
LC CMDS: S (SELECT), W (SHOW),
                                    M(MODIFY),
         P (PURGE), R (REPLICATE), H (HELP), Z (STOP)
    SERV PARM
                   TI TLE
                                           CURRENT WVAL | -8-6-4-2-0+2+4+6+8+ |
   CONUT TSO
                   CONNECTION % UTILIZATION
                                                      80 | < < < < < W
                                                35
                   CONNECTION % UTILIZATION
    CONUT BATCH
                                                      80 | * *
                                                                    W
    CONUT DBAT
                   CONNECTION % UTILIZATION
                                                18
                                                      80 |>>>>
                                                                    W
    THDUT
                   THREAD % UTILIZATION
                                                50
                                                      85
                                                                   W
                                                          |<<<<<
    THDQD CICS
                   QUEUED THREADS
                                                 0
                                                      NZ
                                                                    W
                   CREATE THREAD WAITED
    THDWT
                                                 0
                                                       5
                                                                    W
    EDMPL
                   EDM POOL % UTILIZATION
                                                89
                                                      85
                                                          |>>>>W>>
    BPUTL BPO
                                                76
                                                           ***** W
                   BFR POOL % UTILIZATION
                                                      85
    BPUSE BPO
                   BFR POOL % IN USE
                                                33
                                                      85
                                                                    W
    RI DUT
                   RID POOL % UTILIZATION
                                                 45
                                                      85
                                                                    W
                   ACTI VE LOG % UTI LI ZATI ON
                                                53
                                                                    W
    LOGUT
                                                      85
                                                          |>>>>>
    CSAP
                   CSA % UTILIZATION
                                                95
                                                      80
                                                          |>>>>>W>>>>
    ECSAP
                   ECSA % UTILIZATION
                                                79
                                                      80
                                                               **** W
                                                           **
    DSUTL
                   OPEN DB DATASET % UTIL
                                                24
                                                      85
                                                                    W
    DSOPN
                   DB DATA SETS OPEN
                                                38
                                                      60
                                                          |>>>>
                                                                    W
    DB2DP DBAS
                   DEMAND PAGING
                                               600
                                                    1800
                                                                    W
                                                          1<<<
    LTIME
                   LOCK TIMEOUT FAILURES
                                                 1
                                                       5
                                                                    W
    LDEAD
                   LOCK DEADLOCK FAILURES
                                                 0
                                                      NZ
                                                                    W
    EDMLD DBD
                   AVG EDM REQUESTS/LOAD
                                                 0
                                                      140
                                                                    W
    RWP
                   READS WITH PAGING
                                                 0
                                                      NZ
                                                                    W
    WWP
                   WRITES WITH PAGING
                                                                    W
                                                 0
                                                       NZ.
    GETPG BPO
                   GETPAGE REQUESTS
                                               1144
                                                    1000
                                                                   *W**
```

Warning Status

Figure 26. Active Timer Requests Application

2. Type **X 0N** on the COMMAND line to view only those monitors in exception status.

We'll investigate exceptions more thoroughly later.

3. To find out how to start a monitor (and generate an exception to view):

```
COMMAND ===> SM (Start Monitor)
```

This application displays a list of all available monitor services. (SM is an *application transfer* command that saves your current position and transfers you to another application. You can type a transfer command in any COMMAND line or SERV field.)

Start a Monitor

Monitors look at either resources/system activity (resource monitors) or at workload activity (workload monitors). One workload monitor can be started multiple times to look at different workloads to help isolate specific workload-related problems. Some resource monitors also have parameters to support multiple requests—for example, buffer pool number.

There are many available monitors. You can scroll through the list with PF7/8, sort on any of the columns, or select only those monitors for the area in which you are interested.

To practice starting a monitor:

1. Type **AREA WKLD** on the COMMAND line.

All workload monitor names start with # (for a count) or with an @ (for an average).

2. Type **S** in the line command column next to #SQLM to select a workload monitor.

By selecting #SQLM, you can view some immediate activity because this service measures the number of DML statements issued.

This takes you to the data entry panel, as shown in Figure 27.

```
BMC Software ----- START DB2 WORKLOAD MONITOR REQUEST --- PERFORMANCE MGMT
COMMAND ===>
                                                                TGT ===> DB2G
                       #SQLM - DATA MANI PULATI VE SQL
                                           (Workload Monitor Identifier)
PARM
         ==>
INTERVAL ==> 00: 01: 00 START ==>
                                           ST0P ==>
                                                                     QIS ==> YES
WVAL
                      WMSG ==>
                                            WLI M ==> 10 \quad WI F ==> 1 
                                                                    WIN ==> 1
         ==>
TITLE
                                           (Title)
         ==>
         ==> HOT
                                           (Restart Option: HOT, COLD, PUR, QIS)
RST
PLOTMAX ==>
                                           (Maximum PLOT X-Axis Value)
RANGES
                                           (1-4 Range Distr. Upper Limits)
        ==>
LOG
                                           (NO, ATSTOP, ATPD, ATI NTVL, ATWARN)
Specify Selection Criteria:
   I CHECK ==> NO
                                           (Check elapsed versus Interval time)
   CONNTYPE ==>
                                           (TSO, IMS, CICS, BATCH, CAF or blank)
   DB2PLAN ==>
   DB2AUTH
   DB2CONN ==>
   DB2CORR ==>
   DB2LOC
```

Figure 27. Start DB2 Workload Monitor Data Entry Panel

Using Defaults

3. Define optional workload monitor data collection parameters on the data entry panel using mostly defaults.

a. PARM ==> id

You can specify any name as an ID if you want several requests for this monitor to look at different workloads.

b. INTERVAL ==>

Use the default (00:01:00) of one minute data collection intervals.

c. START ==>

Use the default to start at the next even minute, or type a future time in the format of hh:mm:ss.

Note: The monitors are synchronized to the even minute to make it easier for you to compare the history values they collect.

d. STOP ==>

Use the default of no stop time, or type a time at which you want the monitor to stop in the format of hh:mm:ss, or the number of intervals (minutes).

e. WAL ==> warning threshold value Maximum (n) or Minimum (<n)

A warning message is issued automatically when a sampling exceeds the monitor threshold. Type a low value so you can see a warning. For example, if you expect 100 statements in a minute, type 50. It can be changed to a more appropriate value later.

f. WMSG ==>

If left blank, a warning message is sent to the Journal log when sampling exceeds the monitor threshold (also triggers AutoOPERATOR EXECs). Current warnings are shown on DB2EX. Specify **WT0** to also send a message to the MVS console, or a **TS0 i d** to send a message to that user.

g. Optional fields: (For this exercise, accept the defaults)

WLIM Limit number of warnings sent

WIF Wait n intervals before issuing a warning
WIN Wait n intervals before sending nth warning
RST Monitor reaction if DB2 stops and is restarted

PLOTMAX Specifies maximum value of X Axis on monitor plot display
RANGES Limits for range distribution statistics on plot display
LOG A hardcopy plot is recorded in the BBI-SS PAS Image log

4. Specify workload selection criteria.

```
DB2CONN ==> name, name, name
```

Optional. Type one or more names, where name can be TSO, BATCH, DB2CALL, an IMSID, or a CICS jobname. Leave blank for total workload.

- 5. Press **Enter** to start the monitor and return to the list of monitors.
- 6. Access the Active Timer Requests (AT) display to make more requests.

```
COMMAND===> AT (transfer to Option 3 - MONITORS)
or ===> =3 (a quick jump without saving a return path)
```

7. Type **R** in the line command column next to an active workload monitor to replicate an active monitor request.

This replicates the request parameters.

8. Make another request by typing a unique ID in the PARM field and specifying different selection criteria. Press **PF1** (HELP) for an explanation of the values that can be specified, as shown in Figure 28.

```
BMC Software ----- SET KEYWORDS - WORKLOAD SELECTION CRITERIA ---- TUTORIAL
The following keywords can be used to qualify data collection by a workload
monitor:
CONNTYPE
           TSO | I MS | CI CS | BATCH | CAF | bl ank
           IMSMPP | IMSBMP | IMSTBMP | IMSCTL | DLI | SYSSERV | APLSERV | UTIL (DMR 3.1 and
            These keywords allow workload selection by connection type.
            Blank is the default, which selects all the connection types.
I CHECK
           YES | NO
            If YES is specified, the transaction is discarded if the elapsed
            time is greater than the requested interval time.
            default.
            Data is only available at transaction termination time. YES
            prevents long running transactions from skewing the interval
            statistics.
                                                            continued next page...
```

Figure 28. Sample Help Panel

Getting Help

- 9. Press **Enter** to start the monitor and return to Active Timer Requests.
- 10. Move the cursor to the COMMAND line and continue to press Enter until the new monitors show an ACTIVE status and current measurement values. (Remember, they were synchronized to start at an even minute.)
- 11. Check that at least one monitor is in warning status (line highlighted).
- 12. Use the Modify line command to view the monitor options in effect and to modify any that are preceded by an arrow.

```
LC (Line Command)
M (for Modify)
```

Choose an active monitor and change its threshold value.

If you did not start this monitor, you need special authorization to modify or purge it.

13. Press **PF3** to return to the AT panel.

Look at how the graph of the current value compared to the new threshold has changed.

Note: To stop a monitor, use the **Z** line command.

You now know how to start and modify monitors. The next dialog shows you how to look at the data.

Review Critical Problems

To review critical problems, including those just identified by monitors, return to the **DB2EX** analyzer service.

• Type

Then type **S** in the line command column next to the DB2EX service.

• An even quicker way, if you remember the name of the display you want, is

```
COMMAND ===> EXEC DB2EX
```

Note: If you want a display with one or more parameters, type **EXEC serv parml**, **parm2** on the COMMAND line. For example: **EXEC BFRPL BPO**.

 In a service display, just overtype SERV ===> DB2EX and clear any PARM values.

Note: To print any display while you are looking at it, use **PF4** for screen print. To print a series of displays while you are viewing them, specify **LOG=Y** in line 2.

Exceptions

To review the information on the exception panel:

1. Move the cursor to a message and press **Enter**.

A detailed explanation of the message is shown by the MESSAGES general service.

2. Press PF3 to return to the DB2EX display.

The exception display lists the time the exception occurred and the severity (S for severe, W for warning, I for informational, M for monitor messages). You can enter the severity code in the PARM field to select the messages for display by severity level, as shown in Figure 29.

```
BMC Software -----
                               DB2 EXCEPTIONS
                                                  -----PERFORMANCE MGMT
SERV ===> DB2EX RUNNING 11: 25: 05 INTVL => 3 LOG => N TGT ==> DB2G
PARM ===> S
                         EXCEPTIONS DISPLAYED 1 - 10 of 10 SCROLL=> CSR
EXPAND: MON(DSYS), LINESEL(MSG)
TI ME
         LEV MSGNO
                              EXCEPTI ON
11: 24: 00
          S DZ1090S FINAL ACTIVE LOG DATASET 75% FULL
11: 24: 00 S DZ1110S BSDS REDUCED TO SINGLE MODE
11: 23: 00 S DZ1020S IMS TASK(S) QUEUED FOR THREAD(S)
         S DZ1050S BP(0) DM CRITICAL THRESHOLD REACHED
11: 20: 00
```

Figure 29. DB2 Exceptions Panel

Note:

Severe Messages

You have already learned how to change monitor thresholds. The background exception messages (S, W, I) are user-modifiable for each DB2 system independently in BBPARM member DMRBEX00. This is also where you specify thresholds for runaway query exceptions per connection type (TSO, CICS, and so on). These exceptions can be triggered based on CPU percent, GETPAGEs, CPU total, elapsed time, or updates per commit.

Warning Overview

To return to the list of active monitors (Active Timer Requests - AT) for an overview of important system measurements:

```
1. Type

SERV ==> =3 (transfer to Option 3 - MONITORS)
```

Where warning thresholds are specified, the current value is plotted compared to the threshold (W marker). Arrow signs indicate an increasing (>) or decreasing (<) trend. (Yellow if increasing.)

If the threshold is exceeded, that monitor line is highlighted (red) and a corresponding warning message is shown in the Exceptions display (DB2EX).

Usually, a standard set of monitors is started automatically to collect data whenever the target DB2 is up. Look at all monitors already in warning status or approaching it. For example, if both LOCK TIMEOUT FAILURES and THREAD PERCENT UTILIZATION are high, as shown in Figure 30, the lock contentions are probably caused by a high level of user activity. If only the timeouts are in warning status, a single batch job may be holding too many locks (analyzer LOCKU shows details).




Figure 30. Active Timer Requests Application

Lock
Contention
==>

==>

More Detailed Information

To view more detailed information:

1. If you are interested in one specific area, such as buffer pools, you can narrow down the display to show only the related monitors.

```
COMMAND ===> AREA BUFR (enter AREA alone to see them all again)
```

This makes it easier to concentrate on just the buffer information; for example, to compare the GETPAGE REQUESTS to READ I/O and PREFETCH READ I/O.

2. If you don't see the data you want, you can use the same technique to review the other available monitors for buffer pool information.

```
COMMAND ===> SM (Option 2 - START MONITORS, with stacking)

COMMAND => AREA BUFR
```


You could start additional buffer pool monitors now, just the way you did for #SQLM.

- 3. Press **PF3** to return to the list of active monitors.
- 4. Use the Select line command to view the history collected by a monitor.

```
LC (Line Command)
S (for Select)
```

Choose an active monitor that is showing non-zero for the current value. If the DB2 you are monitoring is very active, there should be several, including the #SQLM monitor you just started. If not, choose one of the MVS-related monitors such as CSAP, CSA Percent Utilization.

This standard **PLOT** display, shown in Figure 31, is used to show the latest 10 values measured by any monitor. For further trending information, the averages for the total monitoring period and the last 2 periods (10 samples each) are also shown. The threshold value is indicated with a W in the graph. Note the **MAXimum** value ever measured and the time it occurred (MAX AT). Rate per second calculations (in this example, paging rates) are shown at the right.



Rates/Second

Maximum Value

Figure 31. Sample PLOT Display

- 5. Press **PF3** to return to the list of active monitors.
- 6. Restrict the display to monitor exceptions only.

COMMAND ===> X ON

7. Press **PF6** to start automatic refresh mode, or type

COMMAND ===> GO

Check to see that the word **INPUT** on line 3 has been replaced by **RUNNING**.

You can start automatic refresh whenever you want to watch for problems or events without continually pressing **Enter**.

- 8. Press **ATTN** to stop refresh and enable command entry.
- 9. Return to the full display.

COMMAND ===> X OFF

10. Change to some other installed MAINVIEW product.

COMMAND ===> product name

IMS, CICS, DB2, AO, CAO, IAO, and MAO are valid names.

This saves your current place and presents the Primary Option Menu of that product. You can even stack copies of MAINVIEW for DB2 by typing **DB2**. This can be useful when you must look at another system or product (for example, to answer a user question about production), but you don't want to lose your place.

11. Return to your original place (Active Timer Requests).

COMMAND ===> =X

You can also press **PF3** in the stacked environment until you exit from its Primary Option Menu.

Windows-Mode Monitor Views

All of the monitor data you have just seen in full-screen displays is also available in windows mode. Both the EZDB2 and EZDSSI Easy Menus have several hyperlinks to monitor views, as shown in Figure 32.

```
17MARO1 16: 32: 36 ----- INFORMATION DISPLAY -----
COMMAND ===>
                                                                 SCROLL ===> CSR
CURR WI N ===> 1
                      ALT WIN ===>
 W1 =EZDSSI ======(ALL=====*====) 17MAR01==16: 37: 22====MVDB2====D===1
                                DB2 SSI Easy Menu
                                                           Threads
                             +----- . Current Threads
  . Overvi ew
 . Exceptions
                          | Place cursor on | . DB2 Summary | menu item and | . Attach Summary | press ENTER | . Connect Summary
 > Buffer Pools
> Status Menu
                           +----- Plan Summary
 Data Sharing Monitors

GBP Group Status In Warning Tools And Menus
GBP Group Activity Summary By Area Set SSI Context

Active Easy Menu
 . Global Lock Stats
                             . Workload Objectives
                                                        > MAIN Menu
 . Global Lockouts
 . Volume I/Os (SSI)
                                                        > Tuni ng Wi zards
  > Page Set Menu
                                                         . Return...
```

Figure 32. DB2 SSI Easy Menu (EZDSSI)

The monitor views are able to provide an SSI perspective on monitor status, as well as the details for one DB2. To see these views:

1. Check to be sure that you have an SSI context in effect. If not, type

CON ALL

2. Hyperlink on **Monitors—In Warning** to see a view of all monitors in warning status in that SSI context, as shown in Figure 33.

Figure 33. Monitors in Warning (DMWARN)

Monitor
Views ==>

See All

Warnings

3. Hyperlink on the **Serv** column to see the equivalent of the full-screen PLOT display, as shown in Figure 34.

Notice that the time intervals here have the most recent times at the top. Each plot view has a hyperlink to a related full-screen display.

Monitor Plot in Windows Mode

17MAR01 12	: 01: 55	- INFORMAT	ION DISI	PLAY							
COMMAND ==	=>	1			SCROL	L ===> CSR					
CURR WIN ==	=> 1 ALT W	/I N ===>									
>W1 =DMWARN	>W1 =DMWARN===D@ELTM===DB2HC====*=====17MAR01==12: 00: 58====MVDB2====D===1										
>>USERS	[El apsed	Events	Parm	ALLWORK						
12: 00: 30		66. 108	3	Appl	SAMPLE						
11: 59: 00		0. 331	6	Warni ng	1.00						
11: 57: 30		0.000	0	Max/Mi n	Maxi mum						
11: 56: 00		0.000	0	Val ue	2304. 72						
11: 54: 30		0.000	0	Ti me	11: 48: 30						
11: 53: 00		0.000	0	Graph Max	2304. 72						
11: 51: 30		16. 022	1	Target	DB2HC						
11: 50: 00		0.000	0	Descript.	Sample DB2	Workl oad					
11: 48: 30	********	2304. 721	2								
11: 47: 00		2. 330	1	Samples	69						
		El apsed	Events	Peri od	00: 15: 00						
Total	*	86. 226	69	Samp Int.	00: 01: 30						
Prev Pd		0.000	0	Start	10: 17: 00						
Curr Pd		3. 361	28	El apsed	01: 43: 30						

Figure 34. Sample Plot View

- 4. Press PF3 twice to return to EZDSSI.
- 5. Hyperlink on **Monitors—Summary by Area** to see a summary of active monitors and their warning status by target and area, as shown in Figure 35.

See Monitors by Target and Area

17MARO1 18: 05: 18	I	NFORMATI	ON DISPLAY							
COMMAND ===> SCROLL ===> CSR										
CURR WIN ===> 1 ALT WIN ===>										
W1 =DMAREAZ=======(ALL=====*=======================										
CMD	Number	Number	Average	Maxi mum	Number					
Target Area	Monitors:	in Warn	0 10 Warni ng	Warni ng	Active					
DB2GC DMVS	2	0	74. 1	95. 2	2					
DB2HC EDM	2	0	40. 0	40.0	2					
DB2HC DMVS	5	1	* 38. 4	136.0	5					
DB2HC LOG	8	0	11. 8	23. 5	8					
DB2HC LOCK	8	0	1. 6	8. 0	8					
DB2HC DSYS	4	0	1. 5	2.4	4					
DB2HC USER	22	0	0.8	3. 7	22					
DB2HC DDF	3	0			3					
DB2HC WKLD	6	1	* 319.3	319. 3	6					
DB2HC BUFR	24	0			24					

Figure 35. Monitor Summary by Area (DMAREAZ)

The hyperlinks provide a list of the monitors.

- 6. Press **PF3** to return to EZDSSI.
- 7. Hyperlink on **Monitors**—**Active** to see a summary of active monitors per target DB2.

Additional views are available to show the monitor data from a realtime (DMONR) or session (DMONS) perspective, while DMONC shows all time perspectives in one view.

8. Press **PF3** to return to EZDSSI.

Workload Objective Views

Special workload monitors are started automatically for you to provide service-level monitoring of response time per workload.

Several default workloads have been predefined for transaction and query connections to DB2, based on connection type. Please refer to Volume 1 of the *MAINVIEW for DB2 User Guide* if you want to add workloads or modify the response time objectives of the existing workloads.

To see if you are meeting your response time goals for the defined workloads:

 From EZDSSI, hyperlink on Monitors—Workload Objectives to review workload objectives, as shown in Figure 36.

Are You
Meeting
Your Goals?

```
17MARO1 11: 59: 40 ----- INFORMATION DISPLAY -----
COMMAND ===>
                                                                SCROLL ===> CSR
CURR WI N ===> 1
                       ALT WIN ===>
 CMD Workload % <= Resp Goal Resp Goal Avg Tran Composite Target --- Name---- 0.....50...100 Goal - % Resp--- Count Workload ------
    ALLWORK 95.6 *********** 1.00 95 0.843 125 SAMPLE
ALLWORK 66.7 ******** 1.00 95 1.428 167 SAMPLE
CAF 100.0 *********** 5.00 90 3.221 2 DB2SAMP
                                                                       DB2H
                                                                       DB1H
                                                                       DB1H
          100. 0 ********** 1. 00 95 0. 543 160 DB2SAMP
    CICS
                                                                       DB1H
                                                        O DB2SAMP
    DBATDB2 00.0
                                    5. 00 90 0. 000
                                                                       DB1H
              00. 0
00. 0
52. 1 ******
    DBATDRDA 00.0
                                    5. 00 90 0. 000 0 DB2SAMP
                                                                       DB1H
    I MSMPP
                                    1.00
                                           95
                                                 0.000
                                                           O DB2SAMP
                                                                       DB1H
    TS0
                                    5.00
                                           90
                                                7. 331
                                                           5 DB2SAMP
                                                                       DB1H
```

Figure 36. Objectives Review (DOBJ)

The graph shows what percentage of all threads in that workload have met the response time goal.

Audit Trail

To view an audit trail of problems throughout the day:

1. Transfer to the Log Display general service (Option L).

```
COMMAND ==> LOG
```

Or press PF5.

All *MAINVIEW for DB2 messages* are shown chronologically, as shown in Figure 37.

Look for Problems

```
BMC Software ----- Log Display ----- General services
COMMAND ===>
                                                              TGT ===> DB2G
LI NE=
           12, 340 LOG= #1 STATUS= I NPUT
                                              TIME= 17: 51: 38 INTV===> 3
12: 11: 00 DS0560W (04) 12: 11: 00 ECSA % UTI LI ZATI ON (TOTAL) = 71 (>70)
12: 12: 00 DS0560W (05) 12: 12: 00 ECSA % UTI LI ZATI ON(TOTAL) = 71 (>70)
12: 12: 55 XS6311I BBI/SESSION FOR - CPS17 - TERMINATED
12: 13: 00 DS0560W (06) 12: 13: 00 ECSA % UTI LI ZATI ON(TOTAL) = 71 (>70) ********
12: 14: 00 DS0560W (07) 12: 14: 00 ECSA % UTI LI ZATI ON (TOTAL) = 71 (>70)
12: 15: 00 DS0560W (08) 12: 15: 00 ECSA % UTILIZATION(TOTAL) = 72 (>70)
12: 16: 00 DS0560W (09) 12: 16: 00 ECSA % UTI LI ZATI ON (TOTAL) = 71
                                                                  (>70)
12: 17: 00 DS0560W (10) 12: 17: 00 ECSA % UTI LI ZATI ON (TOTAL) = 71
                                                                  (>70)
12: 22: 11 XS6304I BBI / SESSI ON FOR - LAA1
                                            - TO -D31X- INITIATED
13: 12: 00 DS0561I 13: 12: 00 ECSA % UTILIZATION(TOTAL) NO LONGER > 70
13: 28: 48 DSNW131I - STOP TRACE SUCCESSFUL FOR TRACE NUMBER(S) 05
13: 28: 49 DSN9022I - DSNWVCM1 '-STOP TRACE' NORMAL COMPLETION
13: 53: 02 DS0560W (01) 13: 53: 00 ECSA % UTILIZATION(TOTAL) = 72
                                                                  (>70)
13: 54: 00 DS0560W (02) 13: 54: 00 ECSA % UTI LI ZATI ON (TOTAL) = 74
                                                                 (>70)
13: 55: 01 DS0560W (03) 13: 55: 00 ECSA % UTILIZATION(TOTAL) = 74 (>70)
13: 56: 00 DS0560W (04) 13: 56: 00 ECSA % UTILIZATION(TOTAL) = 74 (>70)
13: 57: 01 DS0560W (05) 13: 57: 00 ECSA % UTILIZATION(TOTAL) = 74
                                                                  (>70)
13: 58: 00 DS0560W (06) 13: 58: 00 ECSA % UTILIZATION(TOTAL) = 74 (>70)
13: 58: 12 DSN3201I + ABNORMAL EOT IN PROGRESS FOR USER=LGS11
13: 58: 12 CONNECTI ON- I D=DB2CALL CORRELATI ON- I D=LGS11
```

Figure 37. Sample Log Display

You also can request an online audit trail of all *DB2 system messages* by specifying LOG=YES per target DB2 in the DMRBEX00 member of the BBPARM data set.

2. Check for exceptions that occurred in a specific period (Locate Time).

```
COMMAND ==> T 1130
```

3. FIND a specific problem (and press **PF5** for RFIND). For example:

```
COMMAND ==> FIND DWO200W (#SQLM monitor warning)
COMMAND ==> FIND DSNT375 (DB2 deadlock messages)
COMMAND ==> FIND DZ0630W (Runaway TSO query)
COMMAND ==> FIND RUNAWAY (Runaway thread from any connection)
COMMAND ==> FIND DWO (All workload monitor warnings)
```

- 4. Scroll to the left with **PF10** to see the origin of the messages.
 - This value can be used to select a subset of the messages in the Journal log.
- 5. Type **PROFILE** on the COMMAND line to access the Enhanced Journal Facility, as shown in Figure 38.

Select Messages from One Target

BMC Software	Log Display	General services
Included Origins	Excluded Origins	Date 01/03/16 Ti me 12:41:32
DB2G		
		
	/E Profile and return to application discard changes	

Figure 38. Enhanced Journal Facility

- 6. Type your **DB2 target name** (see the TGT field) in the Included Origins column. Return to the Log Display to view the messages only from that DB2.
- 7. Issue the **PROFILE** command again and specify **&TARGET** in the Included Origins column to automatically select the messages from the current target DB2 subsystem. Also specify the **BBI-SS PAS i d** to include MAINVIEW for DB2 messages.

Issue DB2 Commands

If you have the proper authorization in MAINVIEW for DB2 (this is not DB2 authorization), you also can issue DB2 commands from the COMMAND line:

1. Submit a DISPLAY THREAD command.

```
COMMAND ==> - DIS THD(*)
```

The command is automatically routed to the DB2 system shown in the target field. You do not need to know the subsystem recognition character (SSRC) for each DB2.

The command response is shown in Figure 39.

DISPLAY THREAD Command Response

				Log Displ	ay		General services
COMMAND =							TGT ===> DB2G
LI NE=	30, 270	LOG= #1	l S'	TATUS= I NPUT	TI ME=	16: 01: 28	I NTV===> 3
16: 00: 20	- DIS THD	(*)					
16: 00: 20	DSNV401I	- DI SPI	LAY T	HREAD REPORT	FOLLOWS -		
16: 00: 20	DSNV402I	- ACTI V	/E TH	READS -			
16: 00: 20	NAME	ST A	REQ 1	I D	AUTHI D	PLAN	ASI D
16: 00: 20	DB2CALL	T *	143	DB231	D31X		0068
16: 00: 20	DB2CALL	T	30 (OLTF	OLTF		00CF
16: 00: 20	X18H	N	300	0001DSN8I CO	PDRI VER		010D
16: 00: 20	X18H	N	2		BABUSER		00FC
16: 00: 20	CI CSCN3	N	3		BABUSER		0117
16: 00: 20	CI CSCN3	N	0				0117
16: 00: 20	CI CSCN3	N	0				0117
16: 00: 20	CI CSCN3	N	0				0117
16: 00: 20	CI CSCN3	N	0				0117
16: 00: 20	CI CSCN3	N	0				0117
16: 00: 20	CI CSCN3	N	0				0117
16: 00: 20	CI CSCN3	N	0				0117
16: 00: 20	CI CSCN3	N	0				0117
16: 00: 20	CI CSCN3	N	0				0117
16: 00: 20	CI CSCN3	N	0				0117
16: 00: 20	CI CSCN3	N	0				0117
16: 00: 20	CI CSCN3	N	0				0117
16: 00: 20	DI SPLAY	ACTI VE I	REPOR	T COMPLETE			
16: 00: 20	DSN9022I	- DSNVI	OT '-]	DIS THD' NORM	MAL COMPLI	ETI ON	

Figure 39. Log Display

Chapter 3. Monitoring a DB2 Data Sharing Group

Monitoring DB2 data sharing increases the complexity of both the environment and the number of tuning *knobs* that needs to be analyzed and optimized.

The first key requirement is to be able to focus on the level of data that is required to understand how the data sharing group is performing, or to solve a particular problem. Since a data sharing group consists of multiple DB2 members, and these members work together and share resources, viewing each DB2 individually is no longer adequate.

These scenarios show you how to look at all the members concurrently so you can easily compare activity and resource usage across the group, as well as access summarized data for the whole group, such as group buffer pool activity, total database I/O to the shared tables, or global lock contention. Of course, you will still drill down to an individual DB2 member for details as needed.

In this practice session, you

- 1. Define a Single System Image (SSI) context for the data sharing group(s).
- 2. Check on current group activity.
- 3. Look at page set considerations.
- 4. Analyze global lock contention.
- 5. Tune group buffer pools.

Note: This practice session takes approximately one hour to complete.

Define the Group Context

Start this scenario at the EZDSSI menu, described on page 8.

The first thing you need to do is make sure that you have a Single System Image (SSI) context defined for the data sharing group(s) you want to look at:

1. Select the **Set SSI Context** hyperlink (first option under Tools And Menus).

This presents a view of all the defined SSI contexts for MVDB2, as shown in Figure 40.

All Defined MVDB2 SSI Contexts

17MAR2001 16: 17: 22 - COMMAND ===>	INFORMATION DISPLAY	SCROLL ===> CSR
CURR WIN $===> 1$	ALT WIN ===>	
W1 =CONASEL======	==SYSD=====*=====17MAR2001==16: 17: 2	21====PLEXMGR==D====4
CMD SSI Product	Description	Num Num
Context		Targ Act
ALL MVDB2	DB2 SSI context	3 3
ALLDB2 MVDB2	All DB2 Systems	9 9
DBGHC MVDB2	DB2 5.1 Data Sharing Group	2 2

Figure 40. SSI Context Selection List (CONASEL)

2. If you do have a context defined for the data sharing group you want to monitor, all you need to do is hyperlink on the context name. This returns you to EZDSSI with the new context in effect.

If you don't have a context defined, you should define one now. (Even if you have a context defined, you may want to browse a little.) On the COMMAND line, type

CONACTZ

This view lists all SSI contexts (as known by your CAS and any connected CASs). Your CASID is shown on the window information line.

If you have multiple MAINVIEW products installed, here you see one of the most powerful features of SSI—that the same context can be defined for several different MAINVIEW products. Obviously, since each product may look at different target types, the selection criteria can vary.

3. Select the default context of **ALL** for **MVDB2** to hyperlink to the CONACT view.

Now you see each of the defined DB2 target subsystems, as shown in Figure 41.

All Defined DB2 Subsystems

```
17MAR2001 11: 05: 15 ----- INFORMATION DISPLAY -----
COMMAND ===>
                                                           SCROLL ===> CSR
CURR WIN ===> 1
                     ALT WIN ===>
>W1 = CONACTZ==CONACT===SYSD====*====17MAR2001==11:02:43====PLEXMGR==D===3
          Product Target Status
CMD SSI
                                             Description
   Context- ----- Context- of_Target---
           MVDB2
   ALL
                    DBOHC
                             ACTI VE
                                             MAINVIEW for DB2
   ALL
            MVDB2
                     DB1HC
                             ACTI VE
                                              MAINVIEW for DB2
   ALL
            MVDB2
                     DB2HC
                             ACTI VE
                                              MAINVIEW for DB2
```

Figure 41. SSI Context Activity Manager (CONACT)

- 4. Type **CONDEF** on the COMMAND line to access the context definition dialog.
- 5. Browse an example of a context definition.

If a data sharing group context already exists, hyperlink on the SSI context name to see how the target filters were defined. If you don't see the group, select any other context. (You will at least see the default context of ALL.)

- 6. Press **PF3** to return to CONDEF.
- 7. Type **EDIT** on the COMMAND line to obtain an edit lock.
- 8. Type **ADD** on the COMMAND line to display the Add SSI Context Definition panel, as shown in Figure 42.

Add a New Context

```
17MAR2001 11: 10: 14 ------ I NFORMATI ON DI SPLAY -----
COMMAND ===>
                                                       SCROLL ===> CSR
CURR WIN ===> 1
                    ALT WIN ===>
>W1 =CONDEF=======SYSD=====*======(00 EDIT
                                                     ) ====PLEXMGR==D===10
   ----- ADD SSI CONTEXT DEFINITION -----
 COMMAND ===>
 SSI Context ===>
 Description ===>
 Inclusion Filters: (Target is included if any are true)
   1TGTNAME = IN (DB1P, DB2P)
   3
   5
   6
   7
  Equivalent SUBSTITUTION parameters to be used in filter expression:
                %2=TGTSYSTEM %3=TGTPRODUCT %4=TGTSERVER
  %1=TGTNAME
  %5=TGTDESC
 Type END to add the SSI context definition
       CANcel to leave without adding
```

Figure 42. Add SSI Context Definition Panel

In this panel, you define the context name and description and the selection filters for the targets that will be part of this context. Help is available on each of the fields.

You can define several filter conditions, but, in this case, all you will need is to filter by **TGTNAME** (the shorthand for this is %1). Since most sites use some kind of naming convention for the members, you probably only need one filter condition; for example:

```
\%1 = DB?P
```

would include DB2s named DB1P, DB2P, and so forth.

If you prefer, you can define an IN list; for example:

```
TGTNAME IN (DB1P, DB2P)
```

would include only the DB2s named DB1P and DB2P.

Define the Group Context

9. Type the following commands to activate this definition:

```
END (to return to the CONDEF view and complete the ADD)

SAVE (to save the information)

INSTALL (to dynamically activate this SSI context in this CAS)
```

- 10. If there are multiple CASs involved, you need to complete this definition in each CAS. (CASACT will show you a list of CASs and you can type **CON casi d** to switch to another CAS.)
- 11. If they all share the same BBPARM (you still see the new definition after you switch to another CAS), you only need to type

CONDEF EDIT INSTALL

Otherwise, you must repeat the whole set of steps.

Check Current Group Activity

Often you just want to check the health of each member of your data sharing group, and check on the activity levels. The previous dialogs covered how to check on multiple DB2s subsystems and their active threads. For data sharing, all you need to do is focus on just a data sharing group, instead of the default SSI context of ALL used earlier.

To view activity for a data sharing group:

1. You should have already set the context in the previous step. As a shortcut in the future, you can also simply type

CON context (example: CON DBGHC)

2. Now you can select options from the EZDSSI menu to look at just this group. Try the **Status Overview** option again.

Look at Page Set Considerations (I/O / GBP-DEP)

Data sharing means that some or all of the DB2 tables can be accessed concurrently from all members of the group. But the tools provided by DB2 to understand the impact of this are limited. This section shows the power of what SSI can do to make this easier.

To look at page set considerations:

1. One of the key tuning areas in DB2 is I/O analysis. But looking at I/O for shared page sets or volumes from one DB2 member at a time does not give a complete picture.

Select **Volume I/Os (SSI)** from the data sharing section in EZDSSI to see a view of total I/O per volume from all members (PSVOLSSI), as shown in Figure 43.

Volume I/O for the Group

17MAR2001 15: 46: 52 I NFORMATI ON DI SPLAY											
COMMAND =	COMMAND ===> SCROLL ===> CSR										
CURR WIN ===> 1 ALT WIN ===>											
>W1 =PSVOL	SSI ====	=====	(DBGHC====	*======) 17!	MAR2001==15: 4	46: 37====	MVDB2=	==D====13			
	Sync	I/0	Sync Max	Sync Avg		Async	I/0	Async			
Vol ume	I/0s	%	I/O Wait	I/O Wait 0.	20 40	I/0s	%	Pages			
BAB309	6	0.4	31	17 **	****	2	0.0	2			
BAB310	309	19. 9	354	23 **	*****	31	0. 5	104			
BAB311	3	0. 2	38	20 **	****	0	0.0	0			
BAB312	1120	72.3	10322	32 **	******	5732	91.8	44287			
BAB314	8	0. 5	98	29 **	*****	0	0.0	0			
BAB317	36	2. 3	176	27 **	*****	0	0.0	0			
BAB318	5	0.3	27	16 **	****	0	0.0	0			
BAB322	12	0.8	38	14 **	***	449	7. 2	3535			
BAB325	9	0.6	52	16 **	****	0	0.0	0			
BAB330	8	0. 5	104	25 **	*****	0	0.0	0			
BAB331	8	0. 5	30	15 **	***	19	0.3	143			
BAB332	15	1.0	30	10 **	**	8	0. 1	61			
TSG314	11	0. 7	31	16 **	****	3	0.0	14			

Figure 43. Volume I/O SSI Summary—Session (PSVOLSSI)

2. Select **one of the volumes** to see how many page sets are being accessed on that volume from each DB2 (PSVOLSZ), as shown in Figure 44.

Volume I/O per Member

	17MAR2001 COMMAND =)	· I	NFORM	MATION DIS	PLAY	SCROLL ==	
	CURR WIN =	· -							
	>W1 =PSV01	LSZ=====	====(DBGl	HC====*	'=====	===) 17MAR2	001==15: 50	D: 39====MVDB2==	===D====2
]	DB2	Nr.	Sync	I/0	Sync Max	Sync Avg		Async
	Volume Ta	arget	PSs	I/0s	%	I/O Wait	I/O Wait	0 20 40	I/0s
	BAB312 DI	B1HC	13	69	4. 1	10322	188	********+	0
	BAB312 DI	B2HC	17	1102	66. 1	1796	22	*****	5732
- 1									

Figure 44. Volume I/O Summary—Session (PSVOLSZ)

- 3. Select **Nr. PSs** for one of the members to see a list of each page set (PSVOLPS) with I/O data for just that member.
- 4. Press **PF3** to return to PSVOLSZ and select **the volume** instead.

Now you see a list of all page sets on that volume (PSVOLPSZ) and can see how many members access each. The I/O data here shows totals for the group.

5. Select **the volume** once again.

Now the list shows each page set with the I/O data broken down per member (PSVOLPS), as shown in Figure 45.

I/O per Page Set and Member

17MAR2001 15: 53	17MAR2001 15: 53: 44 INFORMATION DISPLAY										
COMMAND ===>					SCROLL	===> CSR					
CURR WIN ===> 1	CURR WIN ===> 1 ALT WIN ===>										
>W1 =PSV0LPS====	>W1 =PSV0LPS=======(DBGHC===*=====) 17MAR2001==15: 53: 33====MVDB2===D===30										
Pa	ge Set	DB2	Sync	Sync Max	Sync Avg						
Volume Database	Object Prt	Target	I/0s	I/O Wait	I/O Wait	0 20 40					
BAB312 DSNDB01	DSNLLX02 001	DB1HC	4	29	12	*					
BAB312 DSNDB01	DSNLLX02 001	DB2HC	11	28	24	**					
BAB312 DSNDB01	DSNSPT01 001	DB1HC	5	28	17	**					
BAB312 DSNDB01	DSNSPT01 001	DB2HC	8	29	15	**					
BAB312 DSNDB01	SPT01 001	DB1HC	3	36	27	***					
BAB312 DSNDB01	SPT01 001	DB2HC	21	40	13	*					
BAB312 DSNDB06	DSNADHO1 001	DB1HC	3	43	17	**					
BAB312 DSNDB06	DSNADHO1 001	DB2HC	23	221	37	****					
BAB312 DSNDB06	DSNATX01 001	DB2HC	13	145	30	***					
BAB312 DSNDB06	DSNATX02 001	DB1HC	12	155	40	****					
BAB312 DSNDB06	DSNATXO2 001	DB2HC	139	98	17	**					

Figure 45. Volume Page Sets (PSVOLPS)

- 6. Press **PF3** to return to EZDSSI; then select the **Tuning Wizards** option, and then the **Data Sharing Wizard**.
- 7. There are several paths you could take on this panel, but first look down at the **Page Set Considerations** section. This provides another way to get to the Volume I/O data you just looked at, but we are now going to select the option to **Check GBP-DEP per Member** to see the level of sharing, as shown in Figure 46.

Check GBP-DEP per Member

	17MAR2001 16: 01: 31 INFORMATION DISPLAY SCROLL ===> CSR										
CURR WIN	CURR WIN ===> 1 ALT WIN ===>										
W1 =WZDS	W1 =WZDSDEP======(DBGHC====*=====)17MAR2001==16:01:30====MVDB2====D====2										
DB2	MVS	GBP	Local	Remote	Log Recs	Ckpts To	Mins. To	Delete			
Target	System	DEP	$R/W\ Int$	R/W Int	To Ckpt	PCLOSE(N)	PCLOSE(T)	Names			
DB1HC	SYSC	4	4	4	50000	5	10	0			
DB2HC	SYSC	4	4	3	50000	5	10	8			
1											

Figure 46. Data Sharing Wizard GBP-DEP/Member (WZDSDEP)

This shows a summary of how many GBP-dependent page sets there are in the group per DB2 member, and includes the key ZPARM values that affect how long a page set remains in this status.

8. Tab the cursor to the column header, **Mins to PCLOSE(T)**, and press **PF1** to get field help on this value, as shown in Figure 47.

Many field help panels, like this one, contain tuning tips in addition to the field definition.

```
17MAR2001 16: 01: 31 ----- INFORMATION DISPLAY -----
COMMAND ===>
                                                           SCROLL ===> CSR
CURR WIN ===> 1
                     ALT WIN ===>
W1 =WZDSDEP=======(DBGHC====*====) 17MAR2001==16: 01: 30====MVDB2====D===2
DB2
         MVS
                     GBP Local Remote Log Recs Ckpts To Mins. To Delete
                     DEP R/W Int R/W Int To Ckpt PCLOSE(N) PCLOSE(T)
Target
         System
         SYSC
DB1HC
DB2HC
         SYSC
                         Hel p
                                    Pseudo-Close Timer Parameter
                                                                     Help
                         Command ==>
                                                           Scroll ==> CSR
                         This value lists the amount of time, in minutes,
                         that must elapse before a data set can be a
                         candidate for pseudo-close (QWP1TMR).
                         ZPARM name: PCLOSET in DSN6SPRM
                         Tuning Tip: The PCLOSEN and PCLOSET parameters are
                                     associated with pseudo-close. PCLOSEN
                                     defaults to 5 system checkpoints and
                                     PCLOSET defaults to 10 minutes. There
                                     is a trade off in setting these
                                     parameters. If these values are set
                                     too high, data sets may remain
                                     GBP-dependent for longer than
                                     necessary and incur unnecessary
                                     performance overhead. If these values
```

Figure 47. Field Help

Press PF3 to return to the Data Sharing Wizard (WZDSHAR) and select the option to Check GBP-DEP by GBP/PS.

```
17MAR2001 16: 18: 16 ----- INFORMATION DISPLAY -----
COMMAND ===>
                                                  SCROLL ===> CSR
                 ALT WIN ===>
CURR \ \ WI \ N \ ===> \ 1
>W1 =PSBPGBPZ=======(DBGHC===*=====)17MAR2001==16:18:15====MVDB2====D===2
Bfrpl DB2
               Nr. GBP
                            Local
                                       Remote
               PSs Dependent R/W Interest R/W Interest Current Changed
 I D
      Target
BP00
      DB1HC
               56 2
                                   1
                                               1
                                                    200
                                                               0
BP00
      DB2HC
                72
                         2
                                    1
                                                1
                                                      88
                                                               1
```

Figure 48. Buffer Pool Page Set GBP-DEP Summary (PSBPGBPZ)

This summarizes the same data, also for the whole group, but now organizes it per group buffer pool and member.

10. Select one pool (**Bfrpl ID**) to see a list of all the open page sets in that pool for all targets.

Tuning Tips

Per Group

Buffer Pool

11. Press **PF3** to return to PSBPGBPZ and then hyperlink on the **GBP Dependent** column to list only the GBP-dependent page sets in that pool (PSGBP), as shown in Figure 49.

Open
Page Sets
in One Pool

	17MAR2001 16: 19: 22 INFORMATION DISPLAY SCROLL ===> CSR										
COMMAND	===>								SCROLL ==	=> CSR	
CURR WIN	===> 1		$ALT\ WIN$	===>	>						
>W1 =PSBPGBPZ=PSGBP===(DBGHC====*=====) 17MAR2001==16: 18: 15====MVDB2====D===4											
P	age Set		DB2		No.	GBP	Local	Remote	VP	VP	
Databas	e 0bj ect	Prt	Target	Ty	Usrs	Dep	Interest	Interest	Current	Changed	
DSN8D51	A DSN8S51E	001	DB1HC	PS	0	Y	R/0	R/W	1	0	
DSN8D51	A DSN8S51E	001	DB2HC	PS	0	Y	R/W	R/0	0	0	
DSN8D51	A DSN8S51P	001	DB1HC	TS	0	Y	R/W	R/0	2	0	
DSN8D51	A DSN8S51P	001	DB2HC	TS	0	Y	R/0	R/W	0	0	

Figure 49. Page Set GBP-DEP Status (PSGBP)

You can not only see which member(s) is GBP-dependent, but also which member(s) has Read/Write Interest and how many pages from that page set are cached in each member's local buffer pool.

Analyze Global Lock Contention

One of the most important issues in data sharing is to control global lock contention, since it not only causes the usual problems of application availability you deal with in one DB2, but can significantly degrade performance in a data sharing group as well.

To analyze global lock contention:

 Press PF3 to return to the Data Sharing Wizard (WZDSHAR) and select Lock Contention Wizard.

The Global Lock Wizard (WZLKGOPT) is displayed, as shown in Figure 50.

Analyze Contention for a Group

17MAR2001 16: 20: 50 I NFOI COMMAND ===> CURR WI N ===> 1) 17MAR2001==16: 20:	SCROLI 49====MVDI	L ===> CSR
** LOCK WI ZARD - GROUP **	Target Values	DB1HC	
. Check Member Contention? (& Select any Member)	Global Locks	Interval 243	Session 12900
. Review History and set TIME? (If Current Interval OK)	Global Suspends.	22	1025
. Any Gross Locks? (2 hrs) (Reduced Concurrency)	GrossLocks	0	0
. List Group Lockouts?	Ti meouts	0	1
(Contention Victims)	Deadl ocks	0	3
. Which Resources Involved? (Data Hot Spots)			
. Compatible Workloads? (Connections Involved)			
Analyze Plans In Lockouts?			
. Blocker Plans			
. Waiter Plans			

Figure 50. Global Lock Wizard (WZLKGOPT)

The Global Lock Wizard helps you step through the analysis of lock contention in DB2 for a data sharing group. It allows you to look at current status or choose an earlier time interval, perhaps one that a user of your system has complained about.

A history of the most important symptoms of lock problems—timeouts and deadlocks—is available, as well as information on system considerations and statistics that can point out potential causes of problems.

2. Select Check Member Contention?.

This view, shown in Figure 51, enables you to see the key indicators for all of the members together, allowing you to identify quickly whether or not there are any global contention issues to analyze. The counts shown are for the time since DB2 started.

Check Member Contention

17MAR2001	17MAR2001 16: 21: 53 INFORMATION DISPLAY									
COMMAND	COMMAND ===> SCROLL ===> CSR									
CURR WIN	CURR WIN ===> 1 ALT WIN ===>									
W1 =WZLI	KGOPT=WZLI	KGMEM(DBGHO	C====*====	===) 17MAI	R2001=	=16: 20: 49====l	MVDB2===	=D===2		
DB2	MVS	Total	Local	Gl obal		% of Group	Gl obal	Fal se		
Target	System	Lockouts	Suspends	Suspends		0 50 100	Locks	Cont.		
DB1HC	SYSC	4	42	1025	53. 9	*****	12900	437		
DB2HC	SYSC	6	85	877	46. 1	*****	27809	348		

Figure 51. Lock Wizard Global Members (WZLKGMEM)

3. From here, you can hyperlink on any one DB2 to analyze its contribution to (or victimization by) global lock contention, as shown in Figure 52.

Member Lock Detail

COMMAND ===>	INFORMATI	ON DI SPLAY	
CURR WIN ===> 1 ALT WI	N ===>		
W1 =WZLKGOPT=WZLKGCON(DBGHC=	===DB2HC===)	17MAR2001==16: 20: 49====MVDB2====D====1	l
Global / Local Contention			
	Interval	Session	
Lockouts			
Ti meouts	0	3	
Deadl ocks	0	3	
Indicators			
% Global Contention	5. 6	1. 5	
. If High - Tune GBP-DEP			
% False Contention	23. 3	39. 7	
. If High-Tune CF (MVMVS)	۵. ۵	39. 7	
. II might fulle of (mvmvs)			
Global Lock Activity			
XES Sync Requests	239	27809	
XES Async Requests	0	7	
I RLM Suspensi ons	23	513	
XES Suspensions	0	16	
Fal se Suspensi ons	7	348	
. More Info			
Local Lock Activity			
Lock Requests	21959	121627	
Lock Suspensions	0	4	
Latch Suspensions	10	57	
. More Info			

Figure 52. Lock Wizard Global/Local Contention (WZLKGCON)

This view provides the information to analyze both global and local lock contention for a selected member. Besides the most critical statistics, both for the current interval and since DB2 startup, the two key indicators of % global contention and % false contention are calculated for you. Thresholds are defined to highlight any value that exceeds the recommended value. Place the cursor on the **% Global Contention** header or fields to see an explanation of the calculation and what it means.

4. Press **PF3** to return to the Lock Wizard - Group panel (WZLKGOPT) and select **List Group Lockouts?** to see a list of the latest timeouts and deadlocks that have occurred in all the members of the group.

The *Global Contention* flag on the right is set to YES when the conflict occurred between threads running on different members, as shown in Figure 53.

Group Lockouts Showing Global Contention

```
17MAR2001 16: 25: 20 ------ INFORMATION DISPLAY ------
COMMAND ===>
                                                         SCROLL ===> CSR
CURR WIN ===> 1
                    ALT WIN ===>
>W1 =LKEVSSI ========(DBGHC===*=====) 17MAR2001==16: 25: 20===MVDB2====D===7
Date / Time Lockout Victim Victim Victim Victim Victim Global
----- Type
                       Member
                               Pl an
                                        AuthID Connect CorrName Cont.
17MAR- 16: 12: 37 DEADLOCK DB2H
                               RXDB2
                                        BOLLAA2 DB2CALL DMRDLK1
                                                                 YES
17MAR- 16: 10: 18 TI MEOUT
                                        BOLLAA2 DB2CALL DMRTMO2
                       DB1H
                               RXDB2
                                                                  YES
17MAR- 16: 10: 15 TI MEOUT
                               RXDB2
                                        BOLLAA2 DB2CALL DMRTMO3
                       DB2H
17MAR- 16: 06: 43 TI MEOUT
                       DB2H
                               RXDB2
                                        BOLLAA2 DB2CALL DMRDLK3
17MAR- 16: 06: 42 DEADLOCK DB2H
                                RXDB2
                                        BOLLAA2 DB2CALL DMRDLK1
                                                                  YES
17MAR-15: 45: 46 DEADLOCK DB2H
                                        BOLLAA2 DB2CALL DMRDLK1
                               RXDB2
                                                                  YES
 17MAR- 15: 45: 26 TI MEOUT
                       DB2H
                                RXDB2
                                        BOLLAA2 DB2CALL DMRDLK3
```

Figure 53. Global Lockout Events (LKEVSSI)

5. Press **PF3** to return to the Lock Wizard - Group panel (WZLKGOPT) and select **Which Resources Involved?** to analyze resource conflicts in the group, as shown in Figure 54.

Group Resource Conflicts

Figure 54. Lockout Resource Summary (LKRESZ)

The first view summarizes all conflicts by table space / index space, so that you can quickly identify the objects with the most contention. The count on the right shows how many conflicts exist between members (global).

6. Hyperlink on a **resource name** showing several conflicts to see a breakdown of these conflicts by specific resource, down to a page or row level (LKRESNRZ).

With this view, hot spots in your tables are immediately visible, as shown in Figure 55.

Figure 55. Lockout Resource Number Summary (LKRESNRZ)

7. Hyperlink on either the **resource name** or the **resource number** to view a list of each lockout event that involved this resource (LKRESD), as shown in Figure 56.

Each Event for This Resource

```
17MAR2001 16: 30: 21 ------ I NFORMATI ON DI SPLAY ------
COMMAND ===>
                                                            SCROLL ===> CSR
                      ALT WIN ===>
CURR WIN ===>1
>W1 =LKRESZ==LKRESD==(DBGHC===*=====)17MAR2001==16:27:12====MVDB2====D===8
 --Resource Name-- Resource Resource Time Lockout Blocker Waiter Gbl
 Database Object Number Type ----- Type
                                                       PlanName PlanName Con
 DSN8D51A DSN8S51E 0000001200 DATAPAGE 16: 12: 37 DEADLOCK RXDB2
                                                                RXDB2
                                                                        Yes
                                                                RXDB2
 DSN8D51A DSN8S51E 0000001200 DATAPAGE 16: 10: 18 TI MEOUT RXDB2
                                                                         Yes
 DSN8D51A DSN8S51E 0000001200 DATAPAGE 16: 10: 18 TIMEOUT
                                                       RXDB2
                                                                RXDB2
                                                                        Yes
 DSN8D51A DSN8S51E 0000001200 DATAPAGE 16: 10: 15 TI MEOUT
                                                       RXDB2
                                                                RXDB2
 DSN8D51A DSN8S51E 0000001200 DATAPAGE 16: 06: 43 TI MEOUT
                                                       RXDR2
                                                                RXDR2
 DSN8D51A DSN8S51E 0000001200 DATAPAGE 16: 06: 42 DEADLOCK RXDB2
                                                                RXDB2
                                                                         Yes
 DSN8D51A DSN8S51E 0000001200 DATAPAGE 15: 45: 46 DEADLOCK RXDB2
                                                                RXDB2
                                                                         Yes
 DSN8D51A DSN8S51E 0000001200 DATAPAGE 15: 45: 26 TI MEOUT RXDB2
                                                                RXDB2
```

Figure 56. Lockout Resource Conflict Detail (LKRESD)

This view helps you quickly determine which plans are involved in the contention and whether or not the problem was occurring only at a particular time, perhaps because of an application affinity problem.

8. Press **PF3** to return to the Lock Wizard - Group panel (WZLKGOPT) and select **Global Blockers/Waiters?** to see which plans are involved in the lockouts, as shown in Figure 57.

Which Plans Involved?

```
17MAR2001 16: 31: 40 ------ I NFORMATI ON DI SPLAY -----
COMMAND ===>
                                                      SCROLL ===> CSR
CURR WIN ===> 1
                  ALT WIN ===>
>W1 =LKBWZSSI =======(DBGHC===*=====) 17MAR2001==16: 31: 37====MVDB2====D===3
 Blocker Blocker Waiter Waiter Timeout Deadlock
                                                     % Conflicts Gbl
PlanName Member PlanName Member Involv. Invovl.
                                                 .... 0....50..100 Con
 RXDB2
        DB1H
                RXDB2 DB2H
                                1 3 36.4 ****
                                                                   4
                                             3 36. 4 ****
 RXDB2
        DB2H
                RXDB2
                        DB1H
                                     1
                                                                   4
 RXDB2
        DB2H
                RXDB2
                        DB2H
                                             0
                                                27. 3 ***
                                                                   0
                                     3
```

Figure 57. Lockout Global Blocker Waiter Summary (LKBWZSSI)

This view lists a summary of blocker/waiter plans and systems. You can identify conflicting plans across multiple data sharing DB2 members. Again, the list of events for a particular combination is available with a hyperlink, so you can quickly check to see if there are any application scheduling problems.

Tune Group Buffer Pools

After global locking, the next most important area of data sharing tuning is to determine whether or not the group buffer pools are the right size and have the correct ratio of directory to data entries to support your workload, based on the amount of inter-DB2 sharing that is occurring.

If any of these resources is lacking, overhead increases in the group buffer pools, the coupling facility, and the local pools. It can also cause unnecessary I/O.

To tune the group buffer pools:

- 1. Press **PF3** to return to the Data Sharing Wizard (WZDSHAR) and select **Review Group** (**Session**) to see an overview of key statistics about
 - Global Contention
 - Group buffer pool performance
 - GBP-dependent page sets
 - Coupling facility activity (castouts, failures)

Data Sharing Member Overview

```
17MAR2001 16: 33: 40 ------ INFORMATION DISPLAY ------
COMMAND ===>
                                                     SCROLL ===> CSR
CURR WIN ===> 1
                   ALT WIN ===>
>W1 =WZDSGMEM======(DBGHC===*=====)17MAR2001==16:33:40===MVDB2====D===2
DB2
        MVS Global Total
                                     Read Hit %
                                                 GBP
        System Cont. % Lockouts ..... 0...50..100
Target
                                                 DEP Castouts Failures
DB1HC
        SYSC
                3. 76 4 14. 0 **
                                                                  0
                                                   1
                                                         4
                               22. 2 **
DB2HC
        SYSC
                   1.57
                                                          23
                                                                  0
```

Figure 58. Data Sharing Wizard Group Members (WZDSGMEM)

This view shows you some of the key indicators per member. This allows you to identify quickly whether or not there are any performance issues to analyze. The counts shown are for the time since DB2 was started.

From here, you can hyperlink on any one DB2 to see all the member statistics for both the current interval and the session data since DB2 startup. Or you can return to the first panel to follow some of the analysis paths.

2. Press **PF3** to return to the Data Sharing Wizard (WZDSHAR) and select **Check GBPs** to access the GBP analysis section of the Data Sharing Wizard.

This decision panel provides options to analyze GBP size and the ratio of directory to data entries, as shown in Figure 59.

```
17MAR2001 16: 35: 20 ----- INFORMATION DISPLAY -----
COMMAND ===>
                                                            SCROLL ===> CSR
                  ALT WIN ===>
CURR WIN ===>1
W1 =WZDSBOPT======(DBGHC====DB*****) 17MAR2001==16: 35: 19====MVDB2====D===1
  ** DATA SHARING WIZARD - GBPs
                                       Group GBP Values
 Check Totals per GBP
    (Select GBP for Detail)
                                                        Interval
                                                                   Sessi on
                                        Read Hit %.....
  . GBP Size Too Small?
                                                             0.0
                                                                       6. 2
                                       Miss-Cache Full. 0
Curr. Chngd Pgs. 0
    (Low Hit% / Cache Full)
                                                                         0
                                       Dir. Reclaims....
                                                               0
                                                                         0
 . Too Few Directory Entries?
   Too Few Directory Entries?
(Reclaims Cause XI/DASD Reads)
                                        XI s/Di r. Recl....
                                                               0
                                                                         0
   Too Few Data Entries?
                                                                        95
    (Castouts More Frequent)
                                        Castouts.....
    (Castout Too Slow)
                                        Write Fail-Stor.
                                                               0
                                                                         0
```

Figure 59. Data Sharing Wizard GBP Options (WZDSBOPT)

GBP Analysis

There are three diagnostic paths here, but, as an example, we are going to follow the path to analyze directory entries. Even if the pools are large enough, a lack of directory entries (used to register each page) can cause problems.

The key indicators on the right are there to help you decide whether or not you need to do additional analysis by following one or more paths. On this panel, all of these values are for the whole group, summarized for all GBPs.

Possible symptoms of too few directory entries are

- The occurrence of directory reclaims so that new pages can be registered
- The even worse consequence—that cross-invalidations of pages in the members' local buffer pools are occurring because of these directory reclaims

If one of these indicators is greater than 0, the field is highlighted in red.

3. Hyperlink on **Too Few Directory Entries** to see a tabular list of all defined group buffer pools, as shown in Figure 60.

GBP Group Overview

17MAR2001 16: 36: 09 INFORMATION DISPLAY SCROLL ===> CSR								
CURR WIN ===> 1 ALT WIN ===>								
>W1 =WZDSGBR======(DBGHC====*=====) 17MAR2001==16: 36: 09====MVDB2====D===9								
GBP	Curr.	Pend.	Di r.	Data	Directory	XI from	XI Read	Read Hit
Name	Ratio	Ratio	Entri es	Entri es	Reclaims	Dir. Recl.	Mi ss	Ratio
BP0	5	5	942	187	0	0	3	6. 2
BP1			0	0	0	0	0	0. 0
BP2			0	0	0	0	0	0. 0
BP4			0	0	0	0	0	0. 0
BP5			0	0	0	0	0	0. 0
BP9			0	0	0	0	0	0. 0
BP11			0	0	0	0	0	0. 0
BP32K			0	0	0	0	0	0. 0
BP32K9			0	0	0	0	0	0. 0

Figure 60. Data Sharing Wizard GBP Directory Entries (WZDSGBR)

Now you can see each group buffer pool with the current definitions, the two key indicators we saw before for all pools (Directory Reclaims and XI from Dir.Recl. columns), and some additional related statistics.

4. From here you can select a single GBP for further analysis, as shown in Figure 61.

GBP Directory Entries (Group)

```
17MAR2001 16: 37: 11 ------ I NFORMATI ON DI SPLAY -----
COMMAND ===>
                                                             SCROLL ===> CSR
CURR \ \ WI \ N \ ===> \ 1
                      ALT WIN ===>
W1 =WZDSGBRD=======(DBGHC====DB******) 17MAR2001==16: 37: 11====MVDB2====D===1
 GBP Directory Entry Analysis - Detail BPO
                                        Interval
                                                           Sessi on
  Reclaims for Directory Entries?
                                               0
                                                                 0
   (GBP Page/Dir Reused)
  Directory Reclaims Causing XI?
                                               0
                                                                 0
    (Local VP Pages Invalidated)
  Also Increasing DASD Reads?
    . Check Members for:
      * XI Miss ==> DASD Reads
  GBP Hit Ratio Low?
   . Check Members for:
      * Low GBP Hit Ratio
  Definitions
   Total Size (4K Blocks)
                                             256
   Directory Entries
                                              942
   Data Entries
                                              187
   Current Ratio
                                              5
   Pending Ratio
                                              5
```

Figure 61. Data Sharing Wizard GBP Directory Detail (WZDSGBRD)

This analysis panel provides details to help you determine whether or not a group buffer pool may have too few directory entries to support its part of the data sharing workload. It addresses the main issue—whether directory reclaims are causing cross-invalidations (XI) and probably increasing I/O.

In this panel, you now see the two key indicators again, but both as interval (current activity) and session (total since DB2 startup) counts.

The answer to the additional question of whether or not this is increasing DASD reads can only be seen by looking at statistics per member instead of at the group level.

5. Hyperlink on **Check Members for XI Miss** to see data sharing session activity counts per member for this group buffer pool, as shown in Figure 62.

17MAR2001 16: 39: 04 ------ I NFORMATI ON DI SPLAY ------COMMAND ===> SCROLL ===> CSRCURR WIN ===> 1ALT WIN ===> W1 =WZDSGBSA=======(DBGHC====*=====) 17MAR2001==16: 39: 02====MVDB2====D===2 GBP DB2 Read XI Read NF Read Changed Clean Sync Read Async Read Hit % Miss Target Miss Writes Writes Total Name Total BP0 DB1HC 14.0 3 40 12 0 50 0 1 13 BP0 DB2HC 22. 2 20 0 18 0

Counts per GBP and Member

Figure 62. Data Sharing Wizard GBP Size Activity (WZDSGBSA)

The XI Read Miss column now shows whether or not any members had to do additional I/O to read in pages lost through reclaims and cross-invalidation. Non-zero counts are highlighted. From here, you can also hyperlink on a GBP to see interval and session counts for that GBP.

You have seen a few of the most important areas for data sharing monitoring. You have used a Single System Image context to enable you to monitor all members of a group, both individually and summarized, and to pull all the relevant data together. Now you have the tools to master the new and complex data sharing performance issues.

Tune Group Buffer Pools

Chapter 4. Tuning an Application with Trace

These scenarios teach you how to navigate easily through the MAINVIEW for DB2 trace setup panels and the displays of trace data, and acquaint you with the trace print utility.

In this practice session, you

- 1. Start an application trace and review the available options.
- 2. Review tips on running your tests with trace.
- 3. Look for application problems using the various trace displays.
- 4. Print a trace report for offline review.

Ite: To complete the first exercise, DB2TRACE=D or ALL must be specified in your BBPARM USERID member. DB2TRACE=ALL must be specified to perform the I/O trace in a later exercise.

You must have authorization to update your BBPARM data set and issue the RESET USERID command (.E A userid) to make these changes. Contact your system administrator if you do not have authorization.

This practice session takes approximately two hours to complete.

Start an Application Trace

To start an application trace, begin by checking the current traces:

1. From the Primary Option Menu, select the **TRACES** option.

```
OPTI ON ===> 4
```

This panel lists all the current traces, as shown in Figure 63. They may be active and collecting data from DB2 (STATus is ACTV), or already complete but not yet purged (STATus is COMP). We will return here later to view your own trace.

Current Traces

ST Command

```
BMC Software ----- CURRENT TRACES -----
                                                          PERFORMANCE MGMT
COMMAND ===>
                                                         TGT ===> DB2G
                                         I NTVL ==> 3
                                 I NPUT
                                                         TIME -- 14: 31: 36
COMMANDS: ST (START APPLICATION TRACE), HT (HISTORY TRACES), TYPE
LC CMDS: S (SELECT), W (SHOW),
                                 M (MODIFY), I (SWITCH), Z (STOP)
         P (PURGE), R (REPLICATE), H (HELP),
                                             Q (QUIESCE LOGGING)
   PARM
            TI TLE
                                     USER ID TARGET TYPE AREA STAT LOG
   SUMMARY DAILY ACCOUNTING TRACE
                                     CIR11
                                             DB2D
                                                    SUM WKLD ACTV
                                                                    ACT
            TRACE OF APDTOO1T
   DETAI L
                                     PWW1
                                             DB2D
                                                    DET
                                                         WKLD ACTV
   BIGELAP ELAPSED OVER 10 SEC
                                     PWW1
                                             DB2D
                                                    SUM WKLD ACTV
```

Figure 63. Current Traces Application

2. Transfer to START APPLICATION TRACE.

```
COMMAND ===> ST
```

You must be authorized to start a trace and to specify certain options. See your system administrator for the trace privileges you have. If you cannot start a trace, just browse these instructions and then go to "Look for Application Problems" on page 69 to view an already active trace.

Specify Options

On the Start DB2 Trace Request panel, shown in Figure 64, you can specify various options for your trace. Many traces can be started using just this first panel. If you want to review additional options, they are available on three more panels that are accessed much like DB2I SPUFI options.

Start Trace

Using Defaults

```
BMC Software ----- START DB2 TRACE REQUEST ----- PERFORMANCE MGMT
COMMAND ===>
                                                            TGT==> DB2G
                                          START ==>
PARM
                    (Trace identifier)
                    (S-Summary, D-Detail) STOP ==>
        ==>
                                                              (hh: mm: ss)
        ==> S
TYPE
                                                              (hh: mm: ss/#min)
STORAGE ==> 1000K (Display buffer size) WRAP ==> YES
                                                            (Y/N wrap buffer)
                    (Y/N log trace)
LOGTRAC ==> N
                                          RST ==> HOT
                                                            (HOT, PUR, QIS)
TI TLE
        ==> DB2 APPLI CATI ON TRACE
Specify Selection Criteria:
DB2PLAN ==>
DB2AUTH ==>
DB2CONN ==>
DB2CORR ==>
DB2LOC ==>
DB2PKG
       ==>
CONNTYPE ==>
Specify additional trace options:
                                        = processed)
Exception Filters => N (Y/N)
Detail Trace Options => N (Y/N)
Trace Log Data Set Options ==> N (Y/N)
                                       Press ENTER to process; END to cancel
```

Figure 64. Start DB2 Trace Request Panel

1. Define a trace using mostly defaults.

a. PARM ==> id

You can specify any name as an ID, but try to make it descriptive. For example, use your initials or an acronym for the application being tested, plus a number to identify the test: JNL003, ABCTEST1, ABC2IO.

b. START ==>

Leave blank to start the trace immediately.

c. TYPE \Longrightarrow **D**

A Detail trace collects the DB2 accounting record and additional events (DB2 performance trace IFCIDs) per thread. The default includes the basic start and end events, plan allocation data, exceptions (like timeouts), sorts, and all the SQL statements. This can be modified on a later panel.

d. STOP ==> 10

This traces for 10 minutes and then stops collecting data. Even if you decide not to log a trace, the data is available for display until the trace is purged.

e. STORAGE ==> 1000K

Use the site default size for the storage buffer (used for online display).

f. WRAP ==> Y

Use the default to wrap the data in the STORAGE buffer if it fills up.

g. LOGTRAC ==> Y

Specify Y to request trace logging. This allocates a VSAM log for this trace. You can recall the data for online display or print reports until you decide to delete the data set.

h. RST ==> HOT

Use the default to restart the trace automatically without loss of data if DB2 goes down and up while you are tracing.

i. TITLE ==> user-specified title

This field is filled in with the default, but you should specify a title that will help you later to identify the contents of this trace.

j. DB2AUTH ==> userid, SYSOPR

Specify your user ID to trace your own tests. Add SYSOPR to trace prefetch reads. You can also specify other selection criteria. For a detail trace, you must specify DB2PLAN or DB2AUTH to limit DB2 tracing. This is subject to DB2 restrictions (1 plan / 8 authids, or vice versa).

Note: If you qualify by plan, prefetch read I/O events cannot be captured.

2. Request the additional trace options to review the other panels.

Exception Filters ==> Y
Detail Trace Options ==> Y
Trace Log Data Set Options ==> Y

3. Press **Enter** to view the next panel.

4. Review the Exception Filters panel, shown in Figure 65, but leave it empty.

Narrowing the Trace

BMC Soft	ware	I	DB2 TRACE EX	XCEPTION FII	LTERS	PERFORM TGT DI	
Speci fy	Exception Fi	lters:					
ELAP	=>	GETPAGE	=>	MAXLOCK	=>	SQLDDL	=>
CPU	=>	PGUPD	=>	LOCKTBL	=>	SQLDYN	=>
ABORT	=>	READI O	=>	I NCRBI ND	=>	SQLCTL	=>
UI DCOM	=>	LOCKSUSP	=>	SQLSEL	=>	SQLFETCH	=>
GETRI O	=>	LOCKESCL	=>	SQLUI D	=>	SQLT0T	=>
RLF	=>	TI MEOUT	=>	RI DFAI L	=>	CLAI MDR	=>
PWAI TI O	=>	PWAI TLK	=>	PWAI TPF	=>	PWAI TOT	=>
PFREQS	=>	PFREADS	=>	HPFAI LS	=>	PRLLGRP	=>
PRLLRED	=>	PRLLFALB	=>				

Figure 65. DB2 Trace Exception Filters Panel

Specifying filters causes thread accounting records that do not meet the qualification to be discarded. The value can be a maximum (n) or a minimum (<n). For example, specifying ELAP ==> 10 only keeps threads with an elapsed time greater than 10 seconds. This is very useful when you are looking for poorly performing applications in an existing DB2 workload.

Note: If you specify several filters, they are ORed. A trace record is retained if any one of the comparisons is valid.

5. Press **Enter** to view the next panel.

6. Review the Detail Trace Options panel, shown in Figure 66.

Adding Detail Events

```
BMC Software ----- PERFORMANCE MGMT
                                                       TGT -- DB2G
COMMAND ===>
Specify additional events:
             ==> Y (Y/N)
   SQL
   SCANS
              ===> N
                     (Y/N)
   I/O
              ==> N (Y/N)
   LOCKS
              ==> N (Y/N)
   DDF
              ==> N (Y/N)
   DDFVTAM
              ==> N (Y/N)
Specify event compression:
   GROUP SQL ===> Y (Y/N)
Specify data collection buffer options:
   TRSI ZE
             ===> 400K
                          (Trace buffer size)
   TRBUFF
              ===> 20
                          (# of trace buffers)
```

Figure 66. Detail Trace Options Panel

```
TRSIZE ==> (value shown is the default for your site)
```

This is the size of a data collection buffer. Without logging, the data collected for one transaction (thread) is limited to two buffers. If you are tracing long-running applications, you may need to increase the size. With logging, multiple buffers can be written per thread and combined automatically when recalled online or printed.

```
TRBUFF ==>
```

You may need to increase this value to trace more concurrent threads or to provide multiple buffers for the logging of long-running applications. The recommended number is three or more times the number of concurrent threads to be traced.

```
GROUP SQL ==> Y
```

Y groups many consecutive identical SQL statements together to save space and make the event trace easier to read; for example, combine many FETCHes.

7. Specify the additional DB2 events you want to trace.

```
SQL
             Y
                    Default is Y for standard application tuning
SCANS
             Y
                    Default is N, specify Y this time
        ==>
I/0
             Y
                    Default is N, specify Y this time
        ==>
LOCKS
             N
                    Default is N, leave as is - very expensive
             N
DDF
        ==>
                    Default is N, needed only for distributed work
DDFVTAM ==>
             N
                    Default is N, needed only for DDF VTAM analysis
```

Each of the other groups of events adds additional overhead. You can specify any combination; for example, SQL and I/O but no SCANS.

8. Press **Enter** to view the next panel.

9. Review the Trace Log Data Set Options panel, shown in Figure 67, but leave the defaults.

Logging the Trace

```
BMC Software ----- TRACE LOG DATA SET OPTIONS ----- PERFORMANCE MGMT
COMMAND ===>
                                                             TGT -- DB2G
Number of Logs
                                (# data sets; >1 for auto switch when full)
               ===> 1
First Log DSN
                 Low level qualifier of DSN must be V01
                 Blank for default: CIR7. DB1D. BLANK. mmmdd. Thhmm. V01
                 Names without quotes will be prefixed with CIR7
Overwrite logs
                ===> Y
                          (Y/N) (Action when all logs used)
                                (Blank for none/PROCLIB member name)
Archi ve PROC
                ===>
Log switch time ===>
                                (HH: MM that a log switch is requested)
                ===> NEW (OLD/NEW) If NEW, specify options below:
Di sposi ti on
                ===> (V00001, V00002, V00003)
Volumes
Primary CYLS
                ===> 5
                                      SMS Storage Class ===> SMSSTOR
Data DSN Suffix ===> D1
                                      SMS Data Class ===> SMSDATA
                                      SMS Management Class ===> SMSMGMT
```

Figure 67. Trace Log Data Set Options Panel

a. Number of Logs ==> 1

Multiple logs are usually needed only for continuous system traces for workload history.

b. First Log DSN ==>

Leave this blank to take the generated default. You must be authorized for dynamic allocation of a trace log. See your system administrator. If you are not authorized, there is a batch job (JXT011) to preallocate a log data set. Then type the name here and change DISPOSITION to OLD.

c. Overwrite Logs ==> Y

Y allows the latest trace data to be kept if it doesn't all fit in the log. N keeps the earliest trace data by quiescing the trace when full.

d. Archive PROC ==>

Leave blank. Not needed for simple single-log traces.

e. Log Switch Time ==>

Leave blank. Not needed for simple single-log traces.

f. Disposition ==> **NEW**

Leave NEW unless you had to preallocate a log.

g. Volumes ==>

This should be filled in with the default volume(s) for your site. If not, specify a volume the MAINVIEW for DB2 product address space (BBI-SS PAS) is allowed to use.

h. Primary Cyls ==>

Use the default.

10. Specify SMS values if necessary in your shop and defaults are not set.

```
SMS Storage Class ==>
SMS Data Class ==>
SMS Management Class ==>
```

11. Press **END** to process the options and return to the first panel.

Activate the Trace

All options are now specified for your trace. The trace options are set to *. If you want to drop the related options you specified, change the * to N. To view them again, change the * to Y.

When all options are * or N:

- 1. Press **Enter** to submit the trace request.
- 2. Press **PF3** to return to the CURRENT TRACES panel.
- 3. Press **Enter** until the status of your trace changes to ACTV.

Data can now be collected. Enter some activity to be traced.

- If the status changes to INV (invalid), there was an error in your request that was not found in the preliminary syntax checking. An example of this kind of error would be a trace log data set allocation error because no space was available on the specified volume. You can see the detailed error messages on the Journal Log (press **PF5** to view).
- If the status changes to QIS (quiesced), the target DB2 is not up.

Review Tips on Tracing Tests

There are many different scenarios for testing. Here are some hints on tracing a few of the most common tests.

- Testing your new application during development
 - Qualify the trace by your own AUTHID. DB2 trace overhead is only incurred for the
 tests of your application. Depending on the number of users of the MAINVIEW for
 DB2 trace in your test DB2 system, you may be able to keep your trace request active
 through several test iterations, consolidating them on one trace log. (Only four detail
 traces can be active at one time.)
 - 2. BIND your program after the trace is started. This captures the text and EXPLAIN data of all static SQL statements in your trace output for reference when analyzing performance. EXPLAIN=YES is not required.
 - 3. If you don't set an automatic stop time when requesting your trace, don't forget to stop it when you have completed testing (use the Z line command in the CURRENT TRACES option). If you have logged the trace data, you should also purge the trace when complete. You can still browse and print the data from the log (HISTORY TRACES option). Otherwise, analyze the data from the online buffers and purge the trace when you are done.
- Analyzing the performance of an existing application
 - 1. Qualify the trace by PLAN.
 - 2. Set automatic start and stop times to cover a time span in which you expect sufficient activity.
 - 3. If the application usually runs well with only a few occurrences of poor performance, specify exception filters to save just those that you need to analyze. For example, select only those with high elapsed or CPU times, or with many GETPAGE requests or I/Os.
- Improving the performance of a bad SQL statement
 - You may have identified a poorly performing SQL statement and now want to try out several different variations in the syntax to determine which is best. If you have RxD2/FlexTools or a similar tool, you can modify and execute the statement directly from the source while in ISPF edit. Otherwise, make the statement executable from SPUFI.
 - 2. Start the trace qualified by your AUTHID.
 - 3. Modify and execute each variation as dynamic SQL. You want to force the thread to terminate so an accounting record will be produced. This is done automatically with RxD2. With SPUFI, you must exit each time to terminate the thread.
 - The trace automatically captures the SQL text, EXPLAIN data (with cost factor), and the accounting record and SQL performance statistics.

You now have all variations captured together in one trace for easy comparison.

Review Tips on Tracing Tests

- Comparing test to production
 - 1. Save the detail trace log from the last test run. Run a short detail trace in production after cutover to compare performance. You can either print batch reports or browse both trace logs in split screen mode.

Look for Application Problems

Now it is time to become acquainted with the trace displays and learn how to use them for application tuning.

There are two options on the Primary Option Menu that display trace data:

Option 4, TRACES

```
OPTION ===> 4 TRACES - Current Application Traces
```

This option lists all currently active or complete trace requests. You have already viewed this option when starting your trace and checking that it started correctly. From this option you can see the trace data as it is being collected. And even after the trace is complete, it stays available here until you purge the trace.

Trace data is posted to the display buffer only when the accounting record is written. If you are tracing a longer running thread (detail), you can view the detail events as they occur with the UTRAC display. (Select the current USERS analyzer display, line select the detail display (DUSER) for your thread, and expand to UTRAC.)

When tracing long-running threads, logging is recommended so that data isn't lost because of buffer shortages. You should also browse the logs to view the data (see next option).

Press **PF3** to return to the Primary Option Menu.

Option 5, HISTORY TRACES

```
OPTION ===> 5 HISTORY TRACES - Historical Trace Data Sets
```

Traces that are logged are also always accessible through this option that lists all known trace log data sets. You can view your trace when it is running, after it is complete, and even after you have purged the original trace request—as long as it is worthwhile to keep the data set. This makes it easy to compare different tests, even a month or two apart, without keeping stacks of paper.

From the log you can recall the data online or print selected reports. The trace log data sets are displayed in descending order by date and time, as shown in Figure 68, so you can easily find a newly created log. If you are looking for an older log, you can sort the display by any of the columns.

```
BMC Software ----- HISTORY TRACES -----
                                                             PERFORMANCE MGMT
COMMAND ===>
                                                           TGT ===> DB2G
                                         TI ME -- 09: 36: 34 SCROLL ===> CSR
COMMANDS: SORT, LOCATE, NEW, STOP, START, TYPE
         S (SELECT), W (SHOW), P (PRINT), D (DELETE), E (RESET)
LC CMDS:
         V (VERIFY), N (NEW), A (ARCHIVE), F (FREE)
DI RECTORY:
             CI R4. LL1X. TRACEDI R
ENTRI ES USED: 1, 209 FREE:
                                                              SCROLL RIGHT >>>
LC DATE----TIME TRACEID TITLE
                                                     USERID
                                                              TGT
                                                                   STAT ACTV
    01/03/29 22:00 LEOTST01 LEOS DETAIL TRACE
                                                     CI R4
                                                              DB2G INV
    01/03/11 21:00 DET1
                            WORKLOAD DETAIL 1
                                                     CIR2
                                                              DB2G
                                                                   USED
                                                                         READ
    01/03/01 00:00 THRDHIST THREAD HISTORY
                                                     BABUSERS DB2G
                                                                   UPDAT WRIT
```

Logged Traces

Figure 68. History Traces Application

Figure 69 summarizes many of the ways you can navigate among the trace displays accessed from either Current Traces, Option 4, or History Traces, Option 5. It is included here for your reference.




Figure 69. Trace Display Service Access

All Trace Entries (DB2 Accounting Records)

Whether selected from Option 4 or 5, all the trace displays are the same, except for a few minor differences. So we will continue here with Option 5.

To view all trace entries in a trace log data set:

1. Sort by USERID.

```
COMMAND ===> SORT US
```

2. Locate your user ID (like ISPF LOCATE).

```
COMMAND ===> L userid
```

3. Select the trace log data set that you just created.

```
LC (Line Command)
S (for Select)
```

The first panel of trace data is displayed, as shown in Figure 70.

Expand from Any Entry for More Information

BMC Software		DB2 TRACE	ENTRI ES			RX AVAI	LABLE
SERV ==> LTRAC	I NPUT	14: 11	: 09 I NTVL=	> 3 L0	G=>N TO	GT ==> DB2	G
PARM ==> PBCRO2						SCROLL=>	
EXPAND: MON(WKLD)	, TOTALS, I/	0- DB/TS,	HI STORY	ENT	RIES IN I	DATASET 1	- 132
AUTH, CON	INECT, PLAN,	TIME, LOC	LI NESEL(S	TRAC)			
19MAR01	PBC	RCP - SQL	/SCAN/IO				
END TIME PLA	N AUTHI D	CONNECT	ELAPSED	CPU	# STMTS	GETPAGE	REASON
09: 17: 52. 76 DSNTI					4		OK TRM
09: 18: 10. 33 DSNTI	A21 CIR8X	BATCH	11 s	220 ms	12	168	OK TRM
09: 18: 32. 78 DSNTI	A21 CIR8X	BATCH	8,768 ms	218 ms	12	162	OK TRM
09: 18: 55. 13 DSNTI	A21 CIR8X	BATCH	9,225 ms	214 ms	12	162	OK TRM
09: 19: 19. 80 DSNTI	A21 CIR8X	BATCH	11 s	216 ms	12	162	OK TRM
09: 19: 44. 59 DSNTI	A21 CIR8X	BATCH	11 s	216 ms	12	162	OK TRM
09: 20: 09. 28 DSNTI	A21 CIR8X	BATCH	11 s	217 ms	12	162	OK TRM
09: 20: 34. 83 DSNTI	A21 CIR8X	BATCH	11 s	215 ms	12	162	OK TRM
09: 21: 00. 54 DSNTI	A21 CIR8X	BATCH	12 s	218 ms	12	162	OK TRM
09: 21: 24. 18 DSNTI	A21 CIR8X	BATCH	10 s	215 ms	12	162	OK TRM
09: 21: 47. 62 DSNTI	A21 CIR8X	BATCH	10 s	217 ms	12	162	OK TRM
09: 22: 05. 21 DSNTI	B21 CIR8X	BATCH	1,117 ms	112 ms	49	59	OK TRM
09: 22: 16. 03 DSNUT	TL CIR8X	UTI LI TY	2,907 ms	163 ms	0	64	OK TRM
09: 22: 17. 93 DSNUT	TL CIR8X	UTI LI TY	1,886 ms	107 ms	0	61	OK TRM
09: 22: 36. 33 DSNTI	A21 CIR8X	BATCH	10 s	204 ms	4	357	OK TRM
09: 22: 43. 14 DSNTI	B21 CIR8X	BATCH	1,981 ms	73 ms	49	32	OK TRM
09: 22: 59. 79 DSNTI	B21 CIR8X	BATCH	1,439 ms	69 ms	49	30	OK TRM

Figure 70. DB2 Trace Entries Display (LTRAC)

LTRAC lists all threads (trace entries) in chronological sequence, with the newest at the bottom. Each entry corresponds to a completed transaction, query, or batch job. There is one entry for each DB2 accounting record. In addition to the thread identifiers (plan, authid, connection), some of the most important performance indicators are shown.

4. Use the scroll keys **PF7** and **PF8** to scroll back and forth in the list.

ENTRIES IN DATASET on line 4 tells you how many threads were traced. (This line says ENTRIES IN BUFFER from a current trace.) Compare the values for ELAPSED, CPU, #STMTS, and GETPAGE and look for high activity.

5. Tab to any entry and press **Enter** to see more detailed information.

Data for One Thread

The Summary Trace Entry display, STRAC, shows summary data for this thread. There are complete activity statistics from the DB2 accounting record. For a detail trace, there also are summaries of the captured detail events, such as SQL statements.

The most critical information is summarized in the base section, shown in Figure 71. It includes

- Identifiers
- Completion status
- · Commits and rollbacks
- A runtime graphic analysis of elapsed and CPU times
- The most important activity counts
- Key indicators of failures or possible problems

Most Critical Information

```
BMC Software ----- SUMMARY TRACE ENTRY ----- RX AVAILABLE
SERV ==> STRAC INPUT 15: 14: 16 INTVL=> 3 LOG=> N TGT==> DB2G
                            ROW 1 OF 129 SCROLL=> CSR
PARM ==> , SEQ=2
EXPAND: MON(WKLD), DETAIL, CURRENT
                                           HIST TGT--- DSN2
     ACCOUNTING: ENV, ELAPSED, SQLCOUNTS, BPOOL, LOCKS, PRLL, PKG, SPAS, DDF
     SUMMARIES: SQL, SCANS, IO/LOCK, SORTS
STOP. \dots O7MAY \ 13: 35: 20. \ 20 \ PLAN. \dots DSN8CCO \ TYPE. \dots ALLI \ ED
RUNTI ME ANALYSI S I N DB2 I N APPL. TOTAL %I N DB2(=) TOTAL(*)
----- 0 ... 25... 50... 75.. 100%
ELAPSED TIME 14 ms 19 ms 33 ms | =======*********** | CPU TIME 12 ms 1,552 us 13 ms | =====* | DB2 WAIT TIME 0 us
DBZ WAIT TIME 0 us
----- ACTIVITY ----- KEY INDICATORS -----
SYNC READS (PRLL=00).....0
                        I/O RSP: SYNC= 45 ms, ASYNC= 107 ms
PREFETCH PAGES READ.....1
UPDATES/COMMI T. . . . . . . . . . . . . . . . 0. 0
BFR HIT RATIOS: ... VP=100%, HP= 0%
```

Figure 71. Summary Trace Entry Display (STRAC)—Base Section

View DB2 Accounting Data

You can scroll down or expand to sections showing complete details on SQL statements by type, lock counts, buffer activity, and parallel I/O and package accounting:

1. Select **ELAPSED** in the ACCOUNTING EXPAND line.

If you run DB2 with Accounting Trace 2 or 3 active, an Elapsed Time Analysis section is displayed, as shown in Figure 72.

Why Are You Waiting?

CATEGORY				ELAPSED		
ELAPSED TIME					(0 25 50 75 100%
IN DB2				∩∩· 12· 30	99. 86	**************
IN APPLICATION					0. 13	1
TOTALS					100. 00	
WAITS IN DB2 (LOCA	1)			00. 12. 40	100.00	
LOCK/LATCH	•	0	115	0 us	0.00	
I/O WAIT	19					
LOG WRITE I/O		0				
OTHER READ I/O	-	0				
OTHER WRITE I/O		0			0.00	
UNIT SWITCH EVEN	-	Ü	u	o us	0.00	!
COMMIT/ROLLBK		0	us	0 us	0.00	!
OPEN/CLOSE	6					1
SYSLGRNG		700				1
DATASPACE MGR	4	243	ms	973 ms	0. 12	<
OTHER	0	0	us	0 us	0.00	i i
ARCH. LOG(QIS)	0	0	us	0 us	0.00	į į
ARCH. READ(TAPE)	0	0	us	0 us	0.00	į į
DRAIN LOCK	0	0	us	0 us	0.00	į į
CLAIM RELEASE	0	0	us	0 us	0.00	İ
PAGELATCH CONT.	0	0	us	0 us	0.00	
SPAS SERVER TCB	0	0	us	0 us	0.00	
WAITS IN DB2 (GLOB	AL)					l i
LOCKS	0	0	us	0 us	0.00	l İ
MSG. PROCESSING	0	0	us	0 us	0.00	
TOTAL WAITS	30	1, 862	ms	56 s	7. 34	*
*NOT ACCOUNTED				00: 11: 44	92. 54	***********

Figure 72. STRAC Elapsed Time Analysis (ELAPSED) Section

The graph tells you at a glance where the most time is being spent—and what you should concentrate on in tuning: more time in the application or in DB2; if in DB2, are the times for I/O, prefetch reads, or lock waits unusually high?

2. Select **BPOOL** in the ACCOUNTING EXPAND line.

This section provides a complete summary of activity for each buffer pool accessed plus totals, as shown in Figure 73.

Buffer Pool Problems?

	BUFFI	ER POOL AC	ΓΙ VI TY -
ACTI VI TY			BP3
GETPAGES			
SYNC READS	25	15	10
GETPAGES/READI O	1. 2	1. 7	0
COND. GP FAI LURES	0	0	0
SEQ. PREFETCH REQS.	0	0	0
LIST PREFETCH REQS.	0		0
DYNAMI C PREFETCHES.	2	0	2
ASYNC PAGES READ	0	0	0
DYNAMI C PREFETCHES. ASYNC PAGES READ PAGES/PREFETCH REQ.	0.0	0 0. 0	0. 0
PAGE UPDATES	3	2	1
IMMEDIATE WRITES	0	0	0
HP SYNC READS		0	0
HP SYNC READ FAIL	0	0	0
HP ASYNC PAGES READ		0	0
HP WRITES	0	0	0
HP WRITE FAILURES	0	0	0
G			ATA SHARIN
CF READS (BUFFER CROSS		LUN)	
- DATA RETURNED	2	-	2
- R/W INTEREST	1	-	1
- NO R/W INTEREST	1	-	1
CF READS (DATA NOT IN			
- DATA RETURNED		-	
- R/W INTEREST	1	-	1
-NO R/W INTEREST		-	1
CF-WRITE (CHGD PGS)	2	-	2
CF-WRITE (CLEAN PG)	1	_	1

Figure 73. STRAC Buffer Pool (BPOOL) Section

The GETPAGE / READ I/O ratio can give you a good indication of synchronous READ efficiency, which directly affects thread elapsed time. However, you should also check the prefetch requests, since some I/O may be occurring asynchronously.

3. Select each of the expand buttons shown in the ACCOUNTING line.

This is all the data you would see with a low-overhead summary trace.

4. The package accounting section is available only if DB2 accounting class 7 is active, and shows a breakdown of elapsed, CPU, and wait times (class 8) per package/DBRM, as shown in Figure 74.

Select a Package for More Information

	PA	ACKAGE / DB	RM OVERVI E	W (ACCTG (CLASSES	7, 8 ONLY)
PACKAGE/					%TOTAL	
DBRM	NO. SQL	CPU TIME	WAIT TIM	ELAPSED	ELAP.	
						0 25 50 75 100
RXSEL1M	5	23 ms	611 ms	860 ms	9. 78	*
RXSEL2M	6	21 ms	514 ms	538 ms	6. 12	*
RXSEL3M	24	38 ms	193 ms	250 ms	2.84	<
RXSEL4M	8	22 ms	765 ms	828 ms	9. 43	*
RXSEL5M	9	24 ms	298 ms	337 ms	3.83	<
RXSEL6M	10	25 ms	363 ms	408 ms	4.64	<
RXSEL7M	11	26 ms	179 ms	211 ms	2.40	<
RXSEL8M	12	28 ms	270 ms	299 ms	3.40	<
RXSEL9M	13	27 ms	288 ms	351 ms	3. 99	<
RXSELAM	14	28 ms	256 ms	286 ms	3. 25	<

Figure 74. STRAC Package/DBRM Overview (PKG) Section

Select one package to see further details in a pop-up display.

5. Press **PF3** to return to STRAC.

View Detail Event Summaries (Detail Trace Only)

Since you started a detail trace, there are several more sections with data summarized from detail event records. You don't have to collect and analyze each type of data separately, the MAINVIEW for DB2 trace does it all for you. You can keep scrolling to see all the data, but there is a quicker way to select just the data you want.

SQL Statement Summary

To view summary data for each SQL statement:

1. Tab through the SUMMARIES EXPAND line to the **SQL** button and press **Enter**.

The SQL Summary is displayed, as shown in Figure 75, with important statistics for each SQL statement, showing totals and averages across all executions. If the plan contains multiple DBRMs, the statements are sorted by package/DBRM (program).

Check Each SQL Statement

			S I NPUT									
SERV ==>					27: 16	INI						
			, SQL, SORT					ROW 1	OF 18	SCRO	_L=> (SR
EXPAND:			ETAIL, HI				DOOL	LOCKC	DDII	DIV	CDAC	
			ENV, ELAP				POOL,	LUCKS,	PKLL,	PKG,	SPAS	s, DDF
	SUMMA	RLES: S	QL, SCANS	, 10/L0	CK, SUI	RIS						
			- SQL SU	MMARY (DETAI L	TRA	CE ONI	LY)				
STMT			AVG.	%	AVG		%	SORT	PA	AGES S	SCANNE	ED
TYPE	STMT	COUNT	ELAPSED						I NDX			
SELECT	3228	1	25 ms	2. 7	1, 930	us	0.3	0	2	1	0	0
SELECT	3347	2	11 ms		4, 047	us	1. 5	0	11	4	0	0
OPEN			172 us	0. 1	170	us	0. 2	0	0	0	0	0
FETCH	3578	11	1, 986 us	2. 3	782	us	1.6	0	19	3	0	0
CLOSE	3664	6	192 us	0. 1	149	us	0. 2	0	0	0	0	0
SELECT	3671	6	1,776 us	1. 1	1, 091		1. 2	0	12	0	0	0
SELECT	3283	1	2,643 us	0.3	1, 888	us	0.3	0	1	0	0	0
OPEN	3299	1	109 us	0.0	107	us	0.0	0	0	0	0	0
FETCH	3313	2	907 us	0. 2	855	us	0.3	0	1	0	0	0
CLOSE	3334	1	142 us	0.0	855 141	us	0.0	0	0	0	0	0
OPEN	3456	1	693 ms	74. 1	414	ms	74. 9	8	23	1187	2	0
FETCH	3468	5	440 us	0. 2	322	us	0.3	0	0	0	6	0
SELECT	4803	1	440 us 1, 269 us	0. 1	1, 121	us	0. 2	0	2	0	0	0
PGM: PO2	5D100	44		83. 9			81.0	8	71	1195	8	0
SELECT	1239	1	1,040 us	0. 1	1,040	us	0. 2	0	2	1	0	0
OPEN	1263	1	66 ms	7. 1	47	ms	8. 6	172	13	6	9	0
FETCH	1273	87	201 us	1. 9	177	us	2.8	0	0	0	2	0
CLOSE	1324	1	250 us	0.0	250	us	0.0	0	0	0	0	0
OPEN	1333	1	15 ms	1.6	14	ms	2.6	7	6	4	5	0
FETCH	1343	5	254 us		254		0. 2	0	0	0	2	0
SELECT	1375	3	1,746 us	0.6	1, 165	us	0.6	0	0	12	0	0
CLOSE	1393	1	126 us	0.0	126	us	0.0	0	0	0	0	0
PGM: PO2	5D200	100		11. 4			15. 0	179	21	23	18	0
SELECT	389	1	38 ms	4. 2	18 134	ms	3. 4	0	10	3	0	0
OPEN	482	1	135 us			us	0.0	0	0	0	0	0
FETCH	489		459 us	0.5	302	us	0. 5	0	1	0	0	0
PGM: PO2	5D300	12		4. 7			3. 9	0	11	3	0	0
** TOTAL	S ***	156						187	103	1221	26	0

Figure 75. STRAC SQL Summary Section

2. Scan the PERCENT ELAPSED column.

The percent tells you how much this statement is contributing to the total thread elapsed time. An average may be high, but if only executed a few times, the statement may not be worthwhile tuning.

3. Scan the SORT RECS column to see which statements invoked a sort.

Although EXPLAIN tells you a sort will be used, it can't tell you whether many rows will be selected and sorted, or just a few. This column does. (Of course, as always, you must adjust this by any differences between your test and production tables.)

4. Scan the PAGES SCANNED - INDX column.

This tells you whether an index was accessed and how many pages were scanned. If this value doesn't meet your expectations, there is more information on index accesses a little further along.

- 5. Check for referential integrity processing. See the PAGES SCANNED REF column.
- 6. Sort the display by PAGES SCANNED DATA.

PARM ==> traceid, SEQ=nn, SQL, SORT=PD

7. Now sort the display by PAGES SCANNED - DATA within Program.

PARM ==> tracei d, SEQ=nn, SQL, **SORT=PDP**

The first characters of the column header are used to request a sort. Adding P as the third character keeps all the statements for each DBRM together. All options are defined in the HELP panels (PF1). (The sort is supported only when you expand to the section, not when you scroll to it.)

8. Place the cursor on one of the SQL statement lines and press Enter.

This pop-up display, shown in Figure 76, shows the complete statistics for that statement, displayed as averages per execution. Where the single line shows total counts of pages scanned, the pop-up display shows averages not only for pages but also rows accessed.

Evaluate SQL Predicates

BMC Software DETAIL TRACE EN SERV ==> STRAC INPUT 10: 22: 51 PARM ==> TEST3, SEQ=000017, SQL EXPAND: SQLTEXT(EXPLAIN)	INTVL=> 3 LOG=> M	TGT	T==> DB2G
STATEMENT: 350 SELECT	NUMBER OF I	EXECUT	TI ONS: 2
PLAN: DSNESPRR ELAPSED:	AVERAGE 2, 794 us	s TO	TAL 5, 588 us
PROGRAM: DSNTI AUL CPU:	AVERAGE 1, 271 us	s TO	TAL 2, 543 us
LOCATION: DB1D			
PACKAGE: SAJUYH2I	AVERA	GES -	
	I NDEX SEQ- I		•
ROWS PROCESSED ALL TYPES	4	2	0
ROWS PROCESSED CORRECT TYPE	4	2	0
ROWS QUALIFIED BY DM (STAGE 1)	3	0	0
ROWS QUALIFIED BY RDS (STAGE 2)	0	0	0
ROWS INSERTED	0	0	0
ROWS UPDATED	0	0	0
ROWS DELETED	0	0	0
PAGES SCANNED	8	2	0
REFERENTI AL INTEGRITY PROCESSING:			
PAGES SCANNED	0	0	0
ROWS DELETED/SET NULL	0	0	0

Figure 76. STRAC SQL Statement Pop-Up Display

These are the statistics that allow you to evaluate the SQL predicates. For example, ROWS QUALIFIED BY RDS are caused by Stage 2 predicates and are more expensive than rows qualified in the first stage by the Data Manager (ROWS QUALIFIED BY DM). Of course, there may be variations per execution depending on host variable values. You will see how to find the statistics per single statement execution later.

- 9. If RxD2 is installed and this is a static SQL statement, the **SQLTEXT(EXPLAIN**) expand button is highlighted. You can select this to view the SQL text from the catalog and access available EXPLAIN data from a PLAN_TABLE or do a dynamic EXPLAIN. This is shown later in Chapter 6, "Using RxD2 with MAINVIEW for DB2" on page 111.
- 10. Press **PF3** to return to STRAC.

Table Space / Index Space Scans

To view table space and index space scans:

1. Tab through the EXPAND line to the **SCANS** button and press **Enter.**

Here you can see a summary of all scans by table space and index space, as shown in Figure 77.

Review
Table Spaces
and
Index Access

SERV ==> PARM ==>	ware STRAC PBCR02, SE MON(WKLD) ACCOUNTIN	CQ=5, SC , DETA IG: ENV	I NPUT CAN, SOF AI L, HI /, ELAF	T 14 RT=DA STORY PSED, S	1: 27: 46 SQLCOUN	I NTVI	L=> 3 R0	LOG=> OW 1 OF	N TGT=	==> DB2 ROLL=>	eg CSR
		I	OATABAS	SE SUM	MARY (D	ETAIL T	TRACE (ONLY) -			
DATABASE	PAGESET								#SCAN		
DD028	S021FT10	8	16	32	193	12	9	185	0	0	0
DD028	S021FT20	13	94	18	110	2	4	16	0	0	0
										0	0
DD028	S021FT40	23	3	3	360	0	0	0	0	0	0
DD028	S021PR10	28	6	12	7	6	1181	44566	0	0	0
DD028	S021PR30	33	33	36	815	11	14	298	0	0	0
DD028	S021UI 10	40	1	2	1	1	1	1	0	0	0
DSNDB07	DSN4K01	3	0	0	0	0	0	0	3	6	0
DSNDB07	DSN4K02	5	0	0	0	0	0	0	1	2	0
DSNDB07	DSN4K03	7	0	0	0	0	0	0	2	4	0
**** TOTA	ALS ****		153	103	1486	35	1221	45105	6	12	0

Figure 77. STRAC Database Summary Section

This data is available only if you requested SCANS on the trace request. It allows you to review the number of rows and pages accessed per page set, and also see which indexes were used.

Lock and I/O Events

To analyze lock and I/O problems:

1. Tab through the EXPAND line to the **IO/LOCK** button and press **Enter**.

This display, shown in Figure 78, is a summary of all lock and I/O activity by this application, shown by table space and index space. The lock data is available with any detail trace. The I/O data is available only if you requested I/O events on the trace request, which can be expensive, depending on the application characteristics.

Analyze Lock and I/O Problems

BMC Software
DATABASE LOCK AND I/O SUMMARY (DETAIL TRACE ONLY)
DATADASE LUCK AND 1/0 SUMMART (DETAIL TRACE ONLT)
LOCKS SYNC. I/O ASYNC I/O
DATABASE PAGESET MAX. SUSP. TM/OUT READ WRITE ELAPSED AVG. ELAP READ PAGES
B1CODB BB040A12 0 0 0 1 0 21 ms 21 ms 0 0
B2CODB BB051012 2 0 0 1 0 18 ms 18 ms 0 0
B3C0DB BB09TS02 3 0 0 0 0 us 0 us 0 0
**** TOTALS **** 5 0 0 2 0 39 ms 19 ms 0 0

Figure 78. STRAC Database Lock and I/O Summary Section

For traces by AUTHID, where SYSOPR is included, you will also see counts for prefetch read requests and the number of pages read for this thread. The other counts are all for synchronous I/O within the application. In other words, the ELAPSED time shown here is part of the total thread elapsed time. Reducing the total number of synchronous I/Os has a direct effect on performance.

We will show you later how to relate these I/Os to the packages/DBRMs and even the SQL statements that caused them. (See "Application I/O Analysis" on page 86.)

Avoiding Expensive Lock Event Traces

A lock trace is usually only requested to analyze a specific locking problem, since it causes a great deal of DB2 overhead and also generates many trace records for MAINVIEW for DB2 to store online and/or log. Therefore, before you decide to trace LOCK events, you should analyze the following detail trace events available in DTRAC (shown next):

LOCK-SUMMARY (display LEVEL=2)

This event appears near the end of the thread processing. It shows the maximum number of page locks held and the highest lock state for each page set (table/index space) accessed.

LOCK-TMO (display LEVEL=1)

This event is shown for any thread terminated by either a timeout or deadlock. It shows the page set involved and identifies the first holder of the lock that was in contention, as well as the state of the lock (for example, held exclusive). It is followed by either a DEADLOCK or LOCK-TMO-DET event (display LEVEL=2) that gives complete details.

LOCK-SUSP (display LEVEL=3)

This event is shown for all lock suspensions. It shows the elapsed time suspended, the page set, the type of entity locked (for example, a data page, index tree, and so on), page number if applicable, and lock state.

Sort Information

To evaluate the impact of sorting:

1. Tab through the EXPAND line to the **SORTS** button and press **Enter**.

A Sort Summary of all the sort activity for this plan execution is displayed, as shown in Figure 79.




Figure 79. STRAC Sort Summary Section

When scrolling through STRAC, this section is at the end of the display. The SORT ELAPSED time allows you to evaluate the impact of sorting on the total thread elapsed time. Since there may be multiple sorts, the values are shown as averages, maximums, minimums, and totals.

Evaluate Impact of Sorting

Look for Application Problems

Now you have seen all the summarized data for one thread by browsing through an STRAC (Summary Trace Entry) display. Even with a low-overhead summary trace, the complete accounting data, elapsed time analysis, buffer pool usage analysis, and DDF information is available. The other summarized data depends on the type of events you decide to trace: SQL, SCANS, IO, LOCKS.

2. Press **PF3** several times until you return to the initial STRAC display.

Another Thread

If you have traced several thread executions, you may now want to view another thread. Look at the PARM field. The SEQ=nnnnnn field shows you the sequence number of this trace entry (accounting record plus summarized details) and allows you to navigate between entries.

To view another thread:

- 1. Press **PF10** to scroll to the next chronological entry.
- 2. Press **PF11** to scroll back to the previous entry.
- 3. Select the **SQLCOUNTS** expand button to view the summary of all SQL statements; then press **PF10** several times.

The display shows the SQL counts for the following threads. This is an easy way to compare particular statistics (such as SQL, elapsed times, or GETPAGEs) for several threads.

Detail Events

There is another level of trace data available for a detail trace. It shows all the traced events for a thread in chronological sequence. To see the detail event statistics:

1. Tab through the EXPAND line to the **DETAIL** button and press **Enter.**

The DTRAC (Detail Trace Entry) display allows you to follow the sequence of events during thread processing, as shown in Figure 80.

Follow the Sequence of Events

SERV ==> PARM ==>	DTRAC TEST3,		I NPUT 7, LEVI	r E L= 2	10: 21 2	1: 48	3 INT	VL=>	3 L(OG=> N TGT=: OF 35 SC	=> DB20	ř
START: 09	: 17: 11	AUTH: JE	EK1	Pl	LAN: DS	SNTI	B21 C	ORR:	DB221	REQ CON	N: BATO	CH
EVENT		AT							=====		======	:===
CREATE- TH	ID	0. 000	45	ms	4. 492	us						
PLAN- ALL	.OC	0.045					I SOL	ATI O	N=CS A	ACQ=USE RE	L=COMMI	T
PKG- ALLOC	;	0.065					*DSNE	SPCS	I S0=0	CS ACQ=USE	REL=CO	MI T
PREPARE	350	0.069	1, 361	${\tt ms}$	26	ms	*RC(0)	C=DT	D/X	PS(10)
BI ND- TEX	T	0.070					*TYPE	=DYN	AMI C	TEXT=SELECT	* FROM	I DS+
EXPLAI N		0.078					*PLAN	=DSN8	8I C22	TEXT=SELECT COST (4. 6)		
EDM- REQ		1. 302	123	ms	3, 964	us	DB=0	00002	258			
OPEN	524	1. 489	204	us	202	us	*RC(0)	C=DT			
			2, 058	${\tt ms}$	6, 247	us				D/X	PS(2)
OPEN- TS		2. 235								S=DSN8S21D		
OPEN- TS										S=XDEPT3		
		3. 549					,					
	532		354				•	,		D/X		
		3. 616					•			D/X		
	532						,			D/X		
		3. 621					•	,		D/X		
		3.672					- '	- /		D/X		
FETCH	532	3.673	337	us	337	115	*RC(0)	C=DT	D/X		

Figure 80. Detail Trace Display for a Transaction (Level 2)—DB2 Requests

The number and type of events shown depend on how much you decided to trace (more events, more overhead). The simplest detail trace captures just the major events and exceptions in the life of the thread. This trace also has SQL, SCANS, and IO.

2. Look at the first event, CREATE-THD.

Events like this, with start and end trace records, are matched and displayed on one line with relative start time, elapsed, and CPU times. Events that occur within another event (like I/O for a scan) are indented.

3. Look at the PARM field.

The SEQ number is the same as that shown on the Summary display (STRAC). But now there is a new parameter of **LEVEL=2**. This parameter allows you to widen or narrow your view of all the traced events. Level 2 shows you the major events (for example, the first event you see is probably PLAN-ALLOCation) and SQL.

4. Change the level to 1 to see just the SQL statements.

PARM ==> tracei d, SEQ=nnnnn, LEVEL=1

Browse through the SQL statements to find one you want to know more about.

5. Tab to that statement and press **PF7** to scroll it to the top (SCROLL => CSR).

6. Change the level to 3 to see SCANS and I/O.

PARM ==> tracei d, SEQ=nnnnn, LEVEL=3

The events always remain in chronological sequence, and the event at the top of the screen remains there. Now you can see all of the events that occurred in processing the SQL statement—index scans, data scans, table space opens, sorts, dynamic SQL text and EXPLAIN data, I/O, and so on.

7. Move the cursor to an SQL statement and press **Enter**.

Here are the statistics for the single SQL statement, shown in Figure 81, available in a pop-up display whenever you need them, but out of the way when browsing the events.

Event Pop-Up

Access More Information

BMC Software DETAIL TRACK SERV ==> DTRAC INPUT 10: 48: 24 PARM ==> ALLNEW51, SEQ=4, LEVEL=2 EXPAND: .SQLTEXT(EXPLAIN)	I NTVL=>	
START: 13: 59: 23 AUTH: BOLSMR3 PLAN: DSNTI	A51 CORR:	DB251REQ CONN: BATCH
EVENT AT ELAPSED CPU	DETAI L	
CREATE 1817 0. 475 14 s 62 ms	*RC(0)	TABLESPACE DEMOS51D
CURSOR: DEMOS51D		=======================================
LOCATION: DB2H		
I SOLATION: READ STABILITY		
REOPTIMIZ: REOPTIMIZATION FOR INPUT VARS		
PACKAGE: SAJUYH2I		
PROGRAM: DSNTI AD	I NDEX	SEQ- DATA
ROWS PROCESSED ALL TYPES	6	6
ROWS PROCESSED CORRECT TYPE	12	6
ROWS QUALIFIED BY DM (STAGE 1)	6	0
ROWS QUALIFIED BY RDS (STAGE 2)	0	0
ROWS INSERTED	0	1
ROWS UPDATED	0	0
ROWS DELETED	0	1
PAGES SCANNED	17	14
REFERENTI AL INTEGRI TY PROCESSI NG:		
PAGES SCANNED	0	0
ROWS DELETED/SET NULL	0	0

Figure 81. DTRAC SQL Statement Pop-Up Display

Any event that has an asterisk at the beginning of the DETAIL column has a pop-up display. The detail column shows the most important data, but many trace records have much more information available. This data varies by event type. For example, for an SQL statement, you see the return code, cursor, indicators about data access (Data/Index/Work = D/X/W), and pages scanned.

You have already seen the SQL pop-up display; the same row/page statistics are available per scan. Some other important pop-up displays are

ck
)

8. Press PF3 three times to return from DTRAC to the LTRAC list of thread entries.

Summarized Data for All Threads

Trace Totals

Now look at data that has been summarized for all the threads that have been traced:

1. In LTRAC, tab to the **TOTALS** expand button and press **Enter** to access the TSTAT display, as shown in Figure 82.

BMC Software -----TRACE STATISTICS ----- RX AVAI LABLE SERV ==> TSTAT INPUT 14: 13: 18 INTVL=> 3 LOG=> N TGT==> DB2G PARM ==> THRDHIST, PLAN=DSNTIA22, TIME=1810-1820 ROW 1 OF 37 SCROLL=> CSR EXPAND: MON(WKLD), HISTORY ACCOUNTING: ELAPSED, SQLCOUNTS, BPOOL, LOCKS, PRLL, SPAS, DDF SUMMARIES: SCANS, IO/LOCK, SORTS, I/O-DB/TS - - - - - - - SUMMARY STATISTICS - ALL TRACE ENTRIES- - - - - - - -----TERMI NATI ONS ---------- ACTI VI TY-----FIRST END. . 22MAY 11. 07. 26. 38 TOTAL AVERAGE MAXI MUM MI NI MUM LAST END. . . 22MAY 12. 04. 39. 68 ELAPSED 02: 05: 18 39 s 00: 26: 40 539 us ELP-DB2 00: 05: 17 1, 662 ms 00: 01: 13 COMMI T/ROLLBK. 188/. 3 0 us NORMAL TERM 189 CPU 35 s 183 ms 2,332 ms 0 us CPU-DB2 23 s 121 ms 2,079 ms 0 us WAITS 00: 04: 14 1, 330 ms 00: 01: 13 0 us -- APPL END......0 3, 926 20 513 GETPAGES 17, 280 90 -- RESI GNON......0 1.857 0 2 -- DBAT INACT.....50 424 70 SYNC RDS 0 -- IFI READ.....0 PFCH PGS 846 4 252 0 UPD/COMT 247 1 24 0 BFR HIT RATIOS: VP= 93%, HP= 0% IN DOUBT TERM 0 - - - - - KEY INDICATORS - - - - - - - - - - - - - - - -TI MEOUTS = 5 BUFFER INCOMPLETE = TOTAL DDL = 5GRANTS / REVOKES = SQL: SELECT= 209, FETCH= 2, 248 SQL: I NS= 155, UPD= 219, DEL= 87 SQL: DYNAMI C(PREPARE) = 247 I/O RSP: SYNC= 19 ms, ASYNC= 106 ms LOCK SUSPENSIONS = 24 RID LIST PROCESSING USED = 314

Figure 82. Summary Statistics for All Trace Buffer Entries (TSTAT)—Base Section

The TSTAT (Trace Statistics) display provides a summary of all traced threads. Much of the data is similar to that shown for one thread in the STRAC display, so just browse through it using the **PF8** key or select the desired accounting data sections from the EXPAND line.

TSTAT can be useful in application tuning when you trace just one plan. It gives you an overview of the performance of the plan to see if you even need to go into further detail analysis of single thread executions. If the average values meet expectations and the maximum and minimum don't vary greatly, you may be able to stop here. Also, TSTAT summarizes the key indicator values to show whether any exceptional conditions, such as RID pool failures, have occurred. After all, the art of performance analysis and tuning is to spend your time where you get the biggest payback.

2. Press **PF3** to return to LTRAC.

Application I/O Analysis

Earlier you looked at the I/O for one thread. Now look at the I/O performed for all the threads traced.

The best way to analyze the I/O workload is to use the series of DBIOx displays, available with an expand button from either LTRAC or TSTAT on an I/O trace, as follows:

 Tab to the I/O-DB/TS expand button and press Enter to access the DBIO display, as shown in Figure 83.

Summarized I/O Events by Page Set

```
BMC Software -----
                          I/O Analysis-HT
                                             -----PERFORMANCE MGMT
SERV ==> DBIO \qquad \qquad INPUT \qquad 11:02:14 \quad INTVL=> 3 \quad LOG=> N \quad TGT==> DB2G
PARM ==> , SORT=DB, TOTAL
                                        LINE 1 OF 19 SCROLL=> CSR
EXPAND: PLAN, AUTH, BPOOL, TIME, CONNECT, LOCATION
EXPAND: LI NESEL(DBTS), CATALOG
OPTION: TOTAL, SYNC, ASYNC
                       CI R2. DB2G. JQSI 0. MAR19. T1818. V01
19MAR01
       TABLE
DATA
                       I/O I/O MAX
                                       AVG
                      COUNT % I OWAIT I OWAIT
BASE
       SPACE
                   DSNDB01 DBD01
                        4 5.6 89 34 | *******
                                 28
                                          28 | ******
DSNDB01 DSNSCT02
                         1 1.4
DSNDB01 DSNSPT01
                         1
                             1.4
                                    17
                                          17
                                  38
                                          31 | ******
DSNDB01 SCT02
                         2
                             2.8
DSNDB01 SPT01
                          4 5.6
                                   351
                                          95
```

Figure 83. I/O Analysis by Database / Table Space Display (DBIO)

The first display (DBIO) summarizes the I/O events by database and table space. You can see the number and percent of I/O per table space and index space, as well as average and maximum I/O wait times. From here, you can use the expand buttons, line selection, and sort parameters to focus on the area of most interest, whether a particular table space, an application, or a specific time period.

2. Tab to **SYNC** on the OPTION line and press **Enter**.

Now only synchronous I/O are displayed. SYNC is now in the PARM field. TOTAL (the default) includes both synchronous and asynchronous I/O. ASYNC shows the prefetch I/O.

3. Tab to **PLAN** and press **Enter**.

Now the I/Os are summarized by plan.

- 4. Tab to the **I/O** % column and press **Enter** to sort the plans with the highest amount of I/O at the top of the list.
- 5. Line select one of the plans and press **Enter**.

The original display by page set is shown again, but is now qualified to show only the I/Os for the selected plan.

Press **PF3** to return to the DBIOP display.

6. Tab to **PKG/PGM** and press **Enter**.

The programs (DBRMs or packages) per plan causing the I/O are now identified.

7. Tab to **SQL** and press **Enter**.

This lowest level now identifies each SQL statement causing I/O, as shown in Figure 84.

SQL Statements Causing I/O

Figure 84. I/O Analysis by SQL Statement (DBIOS)

- 8. At any time you can return to LTRAC (press **PF3** four times from DBIOS). Select a single thread (for example, one with a high elapsed time) and look at the I/O per page set for that one execution summarized in the STRAC IO/LOCK section.
- 9. Select the STRAC **DETAIL** button to view the detail events. Change the display level to **3** to see I/O events.

You can now see each I/O in the chronological sequence in which it was executed, following the SQL statement that caused it, with elapsed and CPU times.

Print a Trace Report

You have now run a trace and viewed it online. However, depending on the results, you may want to have a hardcopy for further analysis. Batch reports can also be valuable tools during an application review meeting.

Note:

This section describes printing a trace, but you may also want to look at the accounting reports produced from SMF data, either from DB2 tables or directly from the extracted DB2 accounting records. See the *MAINVIEW for DB2 Performance Reporter User Guide* for more information.

To begin this exercise:

1. Press **PF3** several times until you return to the History Traces panel (Option 5).

This panel not only provides access to view the trace data online but also offers several line commands to simplify management of the trace log data sets:

- W Show the options used for this trace
- P Generate the JCL to print a batch report
- **D** Delete this data set from the trace directory
- E Reset the log data set for reuse
- V Verify that the directory entry matches the data set contents
- N Add a new data set to the directory (moved from another system)
- **A** Archive the data set (only if an archive started task was specified)
- **F** Free a data set currently being read

Usually you will need only W(SHOW), D(DELETE), and P(PRINT). We are going to concentrate now on P. You can try the others when you need those functions.

All Data per Traced Thread

To print a trace report showing all data per traced thread:

1. Select your trace log data set for print.

```
LC (Li ne Command)
P (for PRINT)
```

The Batch Trace Print panel is displayed, as shown in Figure 85, where you can specify options to print a batch report.

Printing a Trace

```
BMC Software ----- BATCH TRACE PRINT -----
                                                           PERFORMANCE MGMT
COMMAND ===>
                                                             TIME --- 15:00
\label{eq:continuous_potential} \text{Update job statement)} \\
                                                          (END to edit JCL)
Title line 1 ==>
Title line 2 ==>
Data Selection:
From date ==> 16MAR2001 Time ==> 1125
To date ==> 17MAR2001 Time ==> 1412
  PLAN
           ==>
  AUTHI D
  CONNECT ==>
  CORR
           ==>
  LOC
  DB2PKG ==>
REPORT SELECTION:
  LTRAC ==> NO
                                       (YES/NO)
  STRAC ==> NO
                                       (NO, ALL, SUMMARY, section1, section2..)
  DTRAC \ ==> \ NO
                                       (YES/NO)
  POPUP ==> NO
                                       (NO/ALL/SQL/event1, event2, ...)
                  (A/C/L/P/T)
  TSUM ==>
                                       SORT ==> (for any TSUMx)
                   (SUMMARY/ALL/NO) INTERVAL ==> 1H (for TSUMT only)
  TSTAT ==> NO
  DBI 0 ==>
                    (X/A/C/F/L/P/T/xx) I OSORT ==>
                                                         (for any DBIOx)
                                       IOINTVL ==> 10M  (for DBIOT only)
```

Figure 85. Batch Trace Print Panel

2. If this is your first time using this option, you must update your job statements.

```
Update Job ==> Y
```

3. Press **Enter** to display a job statement data entry panel.

Fill in the required information and return using **PF3**.

4. Set the option to N.

5. Fill in the options for a report.

```
TITLE1 ==> any title Optional. Centered in first report header. TITLE2 ==> any title Optional. Centered in second report header.
```

Data Selection is optional. The selection fields can be used to reduce the amount printed from a long trace. The date and time fields are primed with the start and end date-time of the trace.

```
REPORT SELECTION:
LTRAC
       ==> N
STRAC
            ALL
                             Print data per thread traced.
      ==>
DTRAC
            N
      ==>
POPUP
            N
TSUM
        ==>
TSTAT
       ==> N
DBI 0
```

There are many different reports that can be generated, either singly or in combination. Browse "Printing a Trace" in Volume 3 of the *MAINVIEW for DB2 User Guide* for a full explanation of the options and to see sample reports. There is also a sample JCL member DZTBPRNT you can use when you want to generate multiple reports or print reports from SMF data. The control statements for several sample reports are provided in BBSAMP member DZJPnnnn, with comments to point out some of the most useful variations.

The reports are based on printouts of the online displays, so the options are selected using the names of these displays, like LTRAC, STRAC, DTRAC. In this tutorial we have chosen **STRAC=ALL** as the most useful report for application tuning. It shows the following for each thread traced:

- Basic **DB2 accounting record** data
- Environmental Indicators section
- Elapsed Time Analysis section
- SQL Statement Execution Counts section
- Buffer Pool Usage Analysis section, including Global Buffer Pools
- Lock Activity section, including Global Locks
- I/O Parallelism section
- **Routines** section (stored procedures and user-defined functions)
- **DDF Summary** section (if distributed work was done)
- Package/DBRM Overview section (if accounting trace 7 is active)

These sections are included for detail traces:

- SQL Summary section with summary statistics per SQL statement
- Database Summary section with scans per page set
- Database Lock and I/O section with locks and/or I/O data per page set
- **Sort Summary** section (if any sorts were performed)
- 6. Press **Enter** to validate your specifications.

These options are saved in your profile and used to initialize the fields the next time this panel is requested.

7. Press **PF3** to review the generated JCL in edit mode.

The options you specified are inserted into a pattern job DZJPTRAC in BBPROF. You may want to copy this JCL into your own UBBPROF profile data set and modify it.

8. Check the rest of the options.

There are many more print options than can be shown on the panel. The sample job contains a short description of these options. Scroll to the bottom to review them.

9. Submit the job.

```
COMMAND ===> SUB
```

Of course, if you prefer, you can **SAVE** the JCL for later execution, or even **CANCEL** it completely.

10. Press **PF3** to return to the Batch Trace Print panel. You can issue another request now if desired.

Other Examples

When the job is completed, review the output. You may want to try other report combinations too. Here are a few examples:

• For an SQL statement summary per thread, sorted by Average CPU usage, followed by average SQL row processing statistics per statement:

```
LTRAC ==> Y
STRAC ==> SQL, SORTSQL=AC, SQLPOPUP
```

• For a detail event trace per thread, with pop-up displays per SQL statement:

```
LTRAC ==> Y
DTRAC ==> Y
POPUP ==> SQL
```

 For SQL statement text and EXPLAIN data for all dynamic SQL executed or BINDs of static SQL:

```
POPUP ==> (BIND-TEXT, EXPLAIN)
```

• For a summary of I/O counts and wait times per database, table space, and plan (from an I/O trace):

```
DBI 0 ==> XP
```

• To summarize by plan, database, and table space:

```
DBI 0 ==> PX
```

There are also many formatting options you can adjust:

NEWPAGE	Control page breaks
WIDTH	Specify wide (133) or narrow (81) output
LINECNT	Adjust the number of lines printed per page
HEADING	Suppress headings

MAXPAGES Limit the amount of output to prevent an unexpectedly high print volume

Print a Trace Report

Chapter 5. Analyzing the DB2 Workload with Trace

These scenarios teach you how to use the trace displays and the sorting and selection features to pinpoint problem areas and exception threads.

In this practice session, you

- 1. Analyze recent workload history through Option 6—GRAPH.
- 2. Review past history from the trace logs.
- 3. Analyze DB2 I/O per table space.
- 4. Print workload reports for offline review.

Note: This practice session takes approximately one hour to complete.

Analyze Recent Workload History

Sometimes you may need to go back in time to analyze recent history of your DB2 workload; for example:

- To identify system and application exceptions and relate the problems to the threads that caused them
- To analyze the performance of a specific application
- To develop an understanding of the workload profile and spot deviations

Graphic Display of Thread History


MAINVIEW for DB2 sets up a summary trace of the complete DB2 workload that is started automatically and runs continuously. This trace captures the DB2 accounting records and is inexpensive to run. The system administrator may have chosen to log the data, in which case a much longer time span will be available for online recall.

To view a graphic display of this recent thread history:

1. From the Primary Option Menu, select the GRAPH option.

```
OPTI ON ===> 6
```

This panel displays *thread history summarized by 10-minute intervals*, sorted with the most recent intervals at the top of the screen, as shown in Figure 86. The number of threads executed (DB2 accounting records per transaction/query/batch job) is shown, followed by averages per thread of elapsed and CPU times and number of SQL statements and GETPAGEs.



Average Values

Figure 86. Trace Summary by Time Display with GRAPH=AVG

- 2. Press **PF7** to scroll down—and back in time.
- 3. Specify a temporary scroll value to move back to the most recent interval.

```
SERV ==> M
```

Press **PF8** to scroll to the top of the display.

4. To view totals instead of averages:

```
PARM ==> THRDHI ST, SORT=I SD, I=10M, GRAPH=TOT
```

Averages give you a better view of application performance, while the totals show system throughput. Note how the numbers in the column headers change, as shown in Figure 87. These are the maximum values detected, and the graphs show percent of maximum: red / highlighted if > 90 percent.

BMC Software TRACE SUMMARY BY TIMEPERFORMANCE MGMT													
SERV ==> TSUMT INPUT 15: 38: 38 INTVL=> 3 LOG=> N TGT==> DB2G													
PARM ==> THRDHIST, INTVL=10M, SORT=ISD, GRAPH=TOT ROW 1 OF 2 SCROLL=> CSR													
EXPAND: LI NESEL(LTRAC), HI STORY ENTRI ES IN BUFFER 1 - 53													
19MARO1 THREAD HISTORY 19MARO1 - 17MARO1													
I NTERVAL	#THREADS	TOT ELAPSED	TOT CPU	TOT #STMTS	TOT GETPGS								
START	38	03: 17: 59	17 s	616	2, 560								
19: 00: 00	******	<	*	*****	*****								
18: 50: 00	***	**	***	*****	****								
18: 40: 00	*	*	****	****	****								
18: 30: 00	*****	<	****	**	**								
18: 20: 00	****	*	**	****	****								
18: 10: 00	******	*******	*******	*******	******								

Figure 87. Trace Summary by Time Display with GRAPH=TOT

5. Place the cursor on a line with a lot of activity and scroll it to the top with PF7.

For example, this could be a time you need to analyze because a user reported a problem.

6. Now focus on smaller time intervals by changing the INTERVAL(I) value.

```
PARM ==> THRDHI ST, SORT=I SD, I=01M, GRAPH=TOT
```

Any interval in minutes or hours is accepted, but values that divide evenly into 60 (M for minutes) or 24 (H for hours) are easier to read.

7. You can also change the sequence to sort by any column.

```
PARM ==> THRDHI ST, SORT=TG, I =01M, GRAPH=TOT
```

For example, this sorts by TOTAL GETPAGES (use the first letters of the column headers) to help identify times of high buffer activity. Or change ISD to IS to sort by INTERVAL START but with the oldest data on top.

(You could also tab to the column you want to sort on and press Enter.)

8. After the graphics display has helped you easily identify an interval to focus on, you may want to see the numbers behind the graphics.

```
PARM ==> THRDHI ST, SORT=TG, I = 10M, GRAPH=NO
```

The numeric display shows both averages and totals.

This thread history is based on a standard Summary Application Trace. However, if there are other traces you want to view here, all you have to do is change the THRDHIST value in the PARM field to the **traceid** of any other active trace request.

Total Values

Workload Analysis

The most important benefit of providing the thread history feature through the Application Trace is that all of the trace displays are available for navigation so that analysis can be done for any workload group down to the individual threads, or up to one selective summary display, as follows:

- 1. Locate an interval on the display that has at least 20 threads, or the largest you can find. You may need to change the interval back to **I=1H**.
- 2. Use the tab key to place the cursor on that line and press **Enter**.

You are now viewing a list of each individual thread that executed in the selected interval. A TIME keyword has automatically been added to the parameters. This is the LTRAC (List Trace Entries) display that you see when selecting a trace for display (Option 4 or 5), but it is reduced to a subset of threads. (See Figure 69 on page 70.)

3. Tab through the EXPAND line to the **PLAN** button and press **Enter**.

The panel is similar to the one you saw earlier per interval, but now the threads for the one selected interval are *summarized by PLAN*, as shown in Figure 88.

Values for Each Plan

BMC Software TRACE SUMMARY BY PLAN RX AVAILABLE SERV ==> TSUMP INPUT 14: 24: 47 INTVL=> 3 LOG=> N TGT==> DB2G												
PARM ==> THRDHI ST, TI ME=1810-1820, SORT=PL, GRAPH=NO ROW 1 OF 5 SCROLL=> CSR												
EXPAND: LINESEL(LTRAC), HISTORY ENTRIES IN DATASET 1 - 132												
19MARO1 THREAD HISTORY 19MARO1 - 17MARO1												
ENTRY	AVG	AVG	AVG	AVG	TOTAL	TOTAL	TOTAL	TOTAL				
PLAN COUNT	ELAPSED	CPU	#STMTS	GETPGS	ELAPSED	CPU	#STMTS	GETPGS				
DSNESPCS 2	5,516 ms	307 ms	3. 0	70. 0	11 s	615 ms	6	140				
DSNESPRR 3	5,675 ms	446 ms	100.6	109. 3	17 s	1,338 ms	302	328				
DSNTI A22 12	00: 01: 49	281 ms	10.6	169. 0	00: 21: 54	3,379 ms	128	2, 029				
DSNTI B22 11	7,330 ms	122 ms	49.0	34. 0	00: 01: 20	1,351 ms	539	374				
DSNUTI L 2	6,740 ms	186 ms	0.0	72.0	13 s	372 ms	0	144				
DSN8CC22 8	6,380 ms	18 ms	7. 5	10.0	00: 02: 20	398 ms	165	220				
	*** END OF SUMMARY ENTRIES ***											

Figure 88. Trace Summary by Plan Name

You could also have selected one of the other TSUM buttons to summarize by: **AUTHID(AUTH), CONNECTION(CONNECT)**, or **LOCATION(LOC)**.

Note: The GRAPH=NO change you made earlier is carried forward. You can change back to the graphic display any time by overtyping the NO with **YES**.

4. Place the cursor on one of the plans and press **Enter**.

Now you are back at LTRAC with a list of threads executed for that one plan in the interval being investigated. A PLAN keyword has been added to the parameters.

Isolating Problems

You can continue this process of selecting, sorting, and categorizing until you have identified specific exception threads:

1. Select one thread (for example, one with a high elapsed time) and press **Enter**.

Now you have the complete DB2 Accounting record available to you in the STRAC (Summary Trace Entry) display. Here you can see SQL counts, buffer activity (and RID processing failures), lock counts, and elapsed/CPU times, as shown in Figure 89.

Complete Accounting Record at Your Finger Tips

```
BMC Software ----- SUMMARY TRACE ENTRY ----- RX AVAILABLE
SERV ==> STRAC
              INPUT 15: 14: 16 INTVL=> 3 LOG=> N TGT==> DB2G
                              ROW 1 OF 129 SCROLL=> CSR
PARM ==> , SEQ=2
EXPAND: MON(WKLD), DETAIL, CURRENT
                                                HIST TGT--- DSN2
      ACCOUNTING: ENV, ELAPSED, SQLCOUNTS, BPOOL, LOCKS, PRLL, PKG, SPAS, DDF
      SUMMARIES: SQL, SCANS, IO/LOCK, SORTS
STOP. \dots O7MAY \ 13: 35: 20. \ 20 \ PLAN. \dots DSN8CCO \ TYPE. \dots ALLI \ ED
\texttt{ELAPSED}. \dots ... 33 \hspace{0.1cm} \texttt{ms} \hspace{0.1cm} \texttt{ORIG} \hspace{0.1cm} \texttt{PRIM} \hspace{0.1cm} \texttt{AUTH}. \dots ... \texttt{T127} \hspace{0.1cm} \texttt{CORR} \hspace{0.1cm} \texttt{ID}. \dots ... \texttt{GT00PR0B}
______
RUNTIME ANALYSIS IN DB2 IN APPL. TOTAL %IN DB2(=) TOTAL(*)
----- 0 ...25...50...75..100%
ELAPSED TIME 14 ms 19 ms 33 ms | =======********** |
CPU TIME 12 ms 1,552 us 13 ms | ======*

DB2 WAIT TIME 0 us
SYNC READS (PRLL=00).....0
                             I/O RSP: SYNC= 45 ms, ASYNC= 107 ms
PREFETCH PAGES READ.....1
UPDATES/COMMI T. . . . . . . . . . . . . 0. 0
BFR HIT RATIOS: . . . VP=100%, HP= 0%
```

Figure 89. Summary Trace Entry Display (STRAC)—Base Section

- 2. If you run with Accounting Class 2 or 3, don't forget to scroll down or select the **ELAPSED** button to see the graphic display of elapsed times and wait categories.
- 3. The other accounting detail data can be accessed by scrolling or using the expand buttons.
- 4. Press **PF3** to return to LTRAC, the list of completed threads.

5. Tab through the EXPAND line to the **TOTALS** button and press **Enter** to access the Trace Statistics display, as shown in Figure 90.

Qualifiers You've Selected

```
BMC Software -----
                          TRACE STATISTICS
                                                          RX AVAI LABLE
                    INPUT 14: 13: 18 INTVL=> 3 LOG=> N TGT==> DB2G
SERV ==> TSTAT
PARM ==> THRDHIST, PLAN=DSNTIA22, TIME=1810-1820
                                            ROW 1 OF 37 SCROLL=> CSR
EXPAND: MON(WKLD), HI STORY
      ACCOUNTING: ELAPSED, SQLCOUNTS, BPOOL, LOCKS, PRLL, SPAS, DDF
      SUMMARIES: \quad SCANS, \quad I\ 0/LOCK, \quad SORTS, \quad I\ /0-DB/TS
 - - - - - - - SUMMARY STATISTICS - ALL TRACE ENTRIES- - - - -
----- TERMI NATI ONS ------ ACTI VI TY-----
FIRST END. . 22MAY 11. 07. 26. 38
                                     TOTAL AVERAGE MAXI MUM MI NI MUM
                                    LAST END. . . 22MAY 12. 04. 39. 68
NUMBER TRANS.....191
                            ELAPSED 02: 05: 18
                            ELP-DB2 00: 05: 17 1, 662 ms 00: 01: 13
COMMI T/ROLLBK. . . . . 188/. . . . . 3
                                                                 0 us
                            CPU 35 s 183 ms 2, 332 ms CPU-DB2 23 s 121 ms 2, 079 ms
0 us
0 \text{ us}
                            WAITS 00: 04: 14 1, 330 ms 00: 01: 13
0 us
                                     3, 926 20 513
17, 280 90 1, 857
424 2 70
846 4 252
247 1 24
-- APPL END......0
                            SQL
                                                                   0
                            GETPAGES 17, 280
0
-- DBAT INACT.....50
                            SYNC RDS
                                                                    0
                                                        252
 -- IFI READ......0
                            PFCH PGS
                                      247
                            UPD/COMT
                                                                    0
ABNORMAL TERM.....1
IN DOUBT TERM......
                            BFR HIT RATIOS: . . . . . VP= 93%, HP= 0%
- - - - - KEY INDICATORS - - - - - - - - -
TIMEOUTS = 5
BUFFER INCOMPLETE =
TOTAL DDL = 5
GRANTS / REVOKES =
SQL: SELECT= 209, FETCH= 2, 248
SQL: INS= 155, UPD= 219, DEL=
                                 87
SQL: DYNAMI C(PREPARE) = 247
I/O RSP: SYNC= 19 ms, ASYNC= 106 ms
LOCK SUSPENSIONS = 24
RID LIST PROCESSING USED =
                           314
```

Figure 90. Summary Statistics for All Trace Buffer Entries (TSTAT)

The TSTAT (Trace Statistics) display summarizes the data from the selected threads you were just viewing. It provides an easy way to evaluate a problem area that is broader than just one single thread execution.

The values you are looking at now summarize the performance of the one plan you previously selected. Look at the **PARM** field in the third line. You will see the selections you made by selecting lines in TSUMT (**TIME=hhmm—hhmm**) and TSUMP (**PLAN=xxxxxxxx**).

6. To see all activity starting at a specific time, change (or add) the TIME parameter with just a start time.

```
PARM ==> THRDHI ST, TIME=hhmm PLAN=xxxxxxxx
```

7. Press **PF3** to return to LTRAC.

The parameter change is still in effect.

8. To see all activity for a generic group of plans, change (or add) the PLAN parameter using mask characters in the plan name (plus sign for one position, asterisk for multiple positions).

```
PARM ==> THRDHI ST, TI ME=hhmm, PLAN=xxx*
```

The list now shows all plans starting with 'xxx'.

Analyze Recent Workload History

We have gone through examples of using TIME and PLAN, but you can also narrow your view of the workload in the same way using the other selections.

A|AUTHID= To select by user or user group (TSUMA)

C|CONNECT= To select by connection name (TSUMC)

(TSO, BATCH, DB2CALL, cicsid, imsid)

L|LOC= To select by DDF location (TSUML)

D|**DAY**= To select by relative day when the trace spans days

(1 = date of first accounting record in the trace buffer)

(can also be specified as a range of days)

Remember also that if you need to check whether there were any unusual conditions at a particular time, you can go to the Journal log (LOG or PF5) and do a FIND for that time to view DB2 messages and MAINVIEW for DB2 exception messages.

9. Press **PF3** to return to the Primary Option Menu.

Review Past History

In the first dialog, you browsed the recent thread history available in the online buffers. However, this thread history trace is usually set up to log continuously to several trace log data sets, switching automatically when a log is full or when a specified switch time (for example, midnight) is reached. Here are the steps to identify whether logging is defined and to access the older data.

Current Log Data Set

To access the current log data set:

1. From the Primary Option Menu, select the **GRAPH** option.

```
OPTI ON ===> 6
```

As shown before, the recent thread history from the online storage buffer is displayed. (Line 4 shows ENTRIES IN BUFFER.)

2. Look at the expand buttons in line 4.

EXPAND: LINESEL(LTRAC), HISTORY

This HISTORY button tells you that logging is active and there is earlier thread history available to you.

3. Tab through the EXPAND line to the **HISTORY** button and press **Enter**.

You now have the same display of thread history, but it shows all the data on the current log data set. Depending on the way logging is set up, you may be able to see the whole day's activity, or even more. Line 4 now shows **ENTRIES IN DATASET nn - nn**.

All of the display, sort, and selection capabilities you used earlier are available here.

Earlier Log Data Set

To access an earlier log data set:

1. If the time period in which you are interested is not in the current trace logs, you can go further back by recalling data from earlier data sets.

```
SERV ==> =5
                     (transfer to Option 5, HISTORY TRACES)
```

This display lists all available trace log data sets, sorted by the date and time logging was activated to each log, as shown in Figure 91.

```
BMC Software ----- HISTORY TRACES ----- PERFORMANCE MGMT
COMMAND ===>
                                                         TGT ===> DB2G
                                       TI ME -- 09: 36: 34 SCROLL ===> CSR
COMMANDS: SORT, LOCATE, NEW, STOP, START, TYPE
LC CMDS: S (SELECT), W (SHOW), P (PRINT), D (DELETE), E (RESET)
         V (VERIFY), N (NEW), A (ARCHIVE), F (FREE)
             CI R4. LL1X. TRACEDI R
DI RECTORY:
ENTRI ES USED: 1, 209 FREE:
                                                           SCROLL RIGHT >>>
LC DATE----TIME TRACEID TITLE
                                                  USERI D
                                                           TGT STAT ACTV
                                                   CI R4
   01/03/29 22:00 LEOTST01 LEOS DETAIL TRACE
                                                           DB2G INV
   01/03/11 21:00 DET1 WORKLOAD DETAIL 1
                                                   CI R2
                                                           DB2G USED READ
   01/03/01 00:00 THRDHIST THREAD HISTORY
                                                   BABUSERS DB2G UPDAT WRIT
```

Logged Traces

Figure 91. History Traces Application

2. Locate all the data sets for the standard thread history trace.

```
COMMAND ===> SORT TR
                         (Sort by TRACEID)
COMMAND ===> L THRDHIST (Locate the history trace logs)
```

All data sets created by this trace that are still cataloged are listed with the most current ones at the top.

3. Select the data set containing the time period you want to investigate.

```
LC
         (Line Command)
 S
         (for Select)
```

The LTRAC display lists all thread entries, but you can use the expand buttons to summarize, sort, and select the data you need to see.

4. Choose **TSUMT** and then specify **GRAPH=AVG**.

This is the same display you saw for recent history in Option 6—GRAPH, but now it is for any time period kept online—whether a day, week, or year ago.

Analyze DB2 I/O

It is also possible to start other, more detailed, system-wide traces to assist in workload analysis. However, authorization is required for such traces because of the potential overhead, so you may not be able to perform the setup for this dialog. In this case, just browse through the instructions so you understand the features offered. Then you can request such a trace when you need it from your system administrator.

In this example, you analyze I/O usage per page set (table spaces and index spaces). If you run DB2 with Accounting Class 2 or 3, increases in the average I/O wait times may indicate a problem that should be investigated. You can see this value in the ELAPSED TIME ANALYSIS section of TSTAT (select any time period or application of interest), or you may want to do a trend analysis from historical data kept in Performance Reporter tables.

Run a System I/O Trace

Trace I/O Events

To run a system I/O trace:

1. From the Primary Option Menu, select the **I/O** option.

```
OPTI ON ===> 7
```

The I/O Analysis Options panel is displayed, as shown in Figure 92.

```
BMC Software ----- I/O ANALYSIS OPTIONS
                                                    ----- RX AVAI LABLE
COMMAND ==> 7
                                                               TGT ==> DB2G
Display Buffer Pool I/O Data:
  1 I/O BY DB/TS
                  - Display Realtime Data by Database / Tablespace
 2 I/O BY BPOOL - Display Realtime Data by Buffer Pool
  3 \ensuremath{\,\mathrm{I/0}} BY VOLUME - Display Realtime Data by Volume
  4 I/O BY DATASET - Display Realtime Data by Data Set
Display I/O Data from a Trace:
  5 CURRENT TRACES - List Current I/O Traces: n Active, nn Complete
  6 HISTORY TRACES - List All History I/O Traces
Start a DMR I/O trace:
  7 START TRACE
                    - Review Primed Options / Activate (Start Trace Panels)
Print SMF/GTF I/O Traces
  8 DB2 TRACE
                    - Print Instructions
```

Figure 92. I/O Analysis Options Panel

2. Go to the Start Trace request panels.

```
COMMAND ===> 7
```

You need to collect the I/O events for a short time period.

If you do not need to access the following I/O analysis online, read the instructions in Option 8 about writing DB2 I/O trace data to SMF/GTF and printing reports.

3. The required keywords to start an I/O trace are primed in the Start DB2 Trace Request panel.

Specify any additional options necessary for this exercise and start the trace. (Possible additions to primed options are in bold type.)

```
==> IOhhmmss
PARM
                                 Trace ID
TYPE
                                 Detail trace
        ==> D
STORAGE ==> 1000K
                                 Display buffer size
LOGTRAC ==> Y
                                 Log to dynamically allocated data set
       ==> DB2 I/O SYSTEM TRACE Descriptive title
TI TLE
START
       ==> hh: mm ss
                                 Cover peak period
ST0P
                                 Stop after 15 minutes
        ==> 15
DB2AUTH ==> +
                                 Trace all threads
Detail Trace Options ==> *
                                 Next panel shows I/O events selected
   SQL
        ==> N
                                 SQL events turned off to reduce overhead
  I/0
        ==> Y
                                 Specify I/O events
   TRBUFF ==> 50
                                 Increase buffers to trace many threads
```

4. Let the trace run to completion.

Analyze I/O by Page Set

To analyze I/O by page set:

- 1. Return to the I/O Analysis application (Option 7 from the Primary Option Menu).
- 2. Browse the collected trace data.

```
COMMAND ===> 5
                         (Current Traces)
Or, if you logged the trace:
COMMAND ===> 6
                         (History Traces)
```

3. Select the trace you requested (traceid IOhhmmss).

```
(Line Command)
S
        (for Select)
```

The first panel of trace data, a list of all threads executed in this time period, is displayed. However, go first to the summary data for the whole trace.

4. Tab through the EXPAND line to the **I/O-DBTS** button and press **Enter**.

This summarizes all I/O activity by page set for the total DB2 system. It shows total (synchronous and asynchronous) I/O measurements, as shown in Figure 93.

Summarized I/O Events

```
BMC Software ----- I/O Analysis-HT
                                                 -----PERFORMANCE MGMT
SERV ==> DBIO \qquad \qquad INPUT \qquad 11:02:14 \quad INTVL=> 3 \quad LOG=> N \quad TGT==> DB2G
PARM ==> , SORT=DB, TOTAL
                                            LINE 1 OF 19 SCROLL=> CSR
EXPAND: PLAN, AUTH, BPOOL, TIME, CONNECT, LOCATION EXPAND: LI NESEL (DBTS) , CATALOG
OPTION: TOTAL, SYNC, ASYNC
19MAR01
                         CI R2. DB2G. JQSI 0. MAR19. T1818. V01
DATA
        TABLE
                         I/O I/O MAX AVG
        SPACE
BASE
                        COUNT
                               % IOWAIT IOWAIT
                     ------ ---- ---- ---- ms-- - 0 ... 20... 40... 60... 80
DSNDB01 DBD01
                          4 5.6 89 34 | *******
                           1 1.4 28 28 | ******
DSNDB01 DSNSCT02
                                    17
DSNDB01 DSNSPT01
                            1 1. 4
2 2. 8
                                              17 | ****
                                       38
                            1
                                              31 | ******
DSNDB01 SCT02
                                      351 95 | *******
                            4 5.6
DSNDB01 SPT01
```

Figure 93. I/O Analysis by Database / Table Space Display (DBIO)

You can see the number and percent of I/O per table space and index space, as well as the average and maximum I/O sort times. You can select only the synchronous or asynchronous (prefetch) I/Os by tabbing to the **OPTION** line. Only the synchronous I/Os directly affect application response time.

5. Tab to the AVG IOWAIT column and press Enter to sort the highest average delays to the top of the display.

The parameter is changed to SORT=AI. A high average I/O wait may point out possible poor DASD response times.

6. Tab to the MAX IOWAIT column and press Enter to sort the highest maximum delays to the top of the display.

The parameter is changed to SORT=MI. A high maximum value may point out an occasional contention problem that could be masked in the averages.

7. Tab to the I/O COUNT column and press Enter to sort the highest number of I/Os to the top of the display.

The parameter is changed to SORT=I C. Index spaces with high I/O counts may be good candidates for a separate buffer pool configured for index data.

Analyze I/O by Application

I/O problems may be caused by DASD response or contention problems, or they may be caused by the application just doing too many I/Os. To analyze I/O by application:

1. Tab to the **PLAN** button and press **Enter** to access the I/O Analysis by Plan display, as shown in Figure 94.

I/O Summarized by Plan

```
BMC Software ----- I/O Analysis-Plan
                                                     -----PERFORMANCE MGMT
SERV ==> DBI \, OP \qquad \qquad I \, NPUT \qquad 11: \, 29: \, 20 \quad I \, NTVL => \, 3 \quad LOG => \, N \quad TGT ==> \, DB2G
PARM ==> , SO=PL, TOTAL
                                              LINE 1 OF 3 SCROLL=> CSR
EXPAND: PKG/PGM, LINESEL(DBIO), CATALOG
OPTION: TOTAL, SYNC, ASYNC
                           CI R2. DB2G. JQSI O. MAR19. T1818. V01
19MAR01
                          I/O I/O MAX AVG
PLAN
                          COUNT % IOWAIT IOWAIT
                        ------ ---- ---- ms-- -- ms-- 0 ... 20... 40... 60... 80
                           29 40.8 89 19 | ****
6 8.5 38 25 | *****
DSNTI A31
DSNTI B31
                              36 50.7 1028 80 | **************
RXDB2
```

Figure 94. I/O Analysis by Plan Display (DBIOP)

This summarizes all the I/O collected by the trace by plan.

2. Tab to the **I/O** % column and press **Enter**.

This sorts the applications with the highest amount of I/O to the top.

3. Line select one plan.

This returns you to the DBIO display by DB/TS, but shows only the table spaces accessed by that plan.

4. Try out some of the other summarizations, selection, and sorting options to narrow the focus of the displays.

Of course, all the other trace displays are available, including the Lock and I/O Summary per thread (STRAC) and the detail I/O events (DTRAC).

The next section covers printing I/O reports.

Print Workload Reports

Printing workload reports is usually done from the DB2 tables of performance data supported by Performance Reporter. This gives you long-term history and trending, as well as the full flexibility of SQL for defining your own reports in addition to the predefined set. See "Reporting Facilities from DB2 Tables" in the MAINVIEW for DB2 Performance Reporter User Guide for more information.

Also, selective or total accounting reports, in either a short or long format, can be printed from DB2 accounting records extracted from one or more SMF files. For example, you can select from a specific time period or by plan, authorization ID, and so on. The reports also can be summarized by various criteria. See "Reporting Facilities from SMF" in the MAINVIEW for DB2 Performance Reporter User Guide for more information.

However, this data is often not available to answer questions about the workload until the next day. The batch trace print facility is designed to fill the need for quick reports. All the trace summary report formats are available, in any combination.

There are different types of input:

- One or more trace log data sets For example, of the Thread History trace.
- Archived trace logs (without reloading to VSAM) For example, thread history from two weeks ago.
- An SMF history file containing DB2 Accounting records or I/O trace IFCIDs
- The live SMF data sets
- A GTF trace data set

The examples in this dialog are made with the THRDHIST and system I/O traces.

To print a workload report:

1. From the Primary Option Menu, select the **HISTORY TRACES** option.

```
OPTI ON ===> 5
```

2. Locate an entry with a TRACEID of THRDHIST and select it for print.

```
LC
         (Line Command)
 P
         (for PRINT)
```

The Batch Trace Print panel where you can specify options to print one batch report is displayed, as shown in Figure 95.

```
Specify
Options
```

```
BMC Software ----- BATCH TRACE PRINT ----- PERFORMANCE MGMT
COMMAND ===>
                                                      TIME --- 15:00
Update j ob ==> N (Y/N - update j ob statement)
                                                    (END to edit JCL)
Title line 1 ==>
Title line 2 ==>
Data Selection:
From date ==> 16MAR2001 Time ==> 1125
To date ==> 17MAR2001 Time ==> 1412
  PLAN
         ==>
  AUTHI D ==>
  CONNECT ==>
  CORR
         ==>
  LOC
          ==>
  DB2PKG ==>
REPORT SELECTION:
  LTRAC ==> NO
                                   (YES/NO)
  STRAC ==> NO
                                   (NO, ALL, SUMMARY, section1, section2..)
  DTRAC ==> NO
                                   (YES/NO)
  POPUP ==> NO
                                   (NO/ALL/SQL/event1, event2, . . . )
  IOINTVL ==> 10M (for DBIOT only)
```

Figure 95. Batch Trace Print Panel

You can also use the sample JCL **DZTBPRNT** to tailor and submit a set of reports. This JCL is set up so that it can invoke several sample report members that explain many of the available print options.

3. If this is the first time you are using this option, you may want to update your job statements first (Update Job ==> Y).

4. Fill in the options for a report.

```
REPORT ==> traceid
                      Specify any name. Used as the output DD.
DDNAME ==>
                      Optional.
TITLE1 ==> any title Optional. Centered in first report header.
TITLE2 ==> any title Optional. Centered in second report header.
```

Data Selection is optional, but can be used to reduce the amount printed. The date and time fields are primed from the trace log data set.

```
REPORT SELECTION:
LTRAC ==> N
STRAC ==> N
DTRAC ==> N
POPUP ==> N
TSUM
       ==> T
                        SORT
                                ==>
                        INTERVAL ==> 30M
TSTAT ==> SUMMARY
```

5. Press **Enter** to validate your specifications.

These options are saved in your profile and used to initialize the fields the next time this panel is requested.

6. Press **PF3** to review the generated JCL in edit mode.

The options you specified are inserted into a pattern job DZJPTRAC in BBPROF. You may want to copy this JCL into your own UBBPROF data set and modify it.

7. Check the other options and add if desired; for example:

```
TSUM=T, I = 30M, GRAPH=TOT
```

Add the option to graph the totals instead of printing values. There are many other options that cannot be shown on the panel. Refer to "Printing a Trace" in Volume 3 of the MAINVIEW for DB2 User Guide.

8. Submit the job.

```
COMMAND ===> SUB
```

If you prefer, you can **SAVE** or **CANCEL** the JCL.

9. Press **PF3** to return to the Batch Trace Print panel.

You can make another request now if desired.

When the job completes, review the output. This gives you a graphic summary of total DB2 activity for the selected time period in 30-minute intervals, followed by a summary of the activity.

Here is another example:

```
LTRAC ==> Y
STRAC ==> SUMMARY
                           (Add , DDF if DDF is active)
```

This provides the complete DB2 Accounting information per thread. You may want to use the data selection options to limit the output.

To print an I/O report from the system I/O trace log or from an SMF/GTF data set that has DB2 I/O IFCIDs 6 - 10:

DBI 0=X	Summarize l	by	database/table	space
DBI 0=XP	Summarize l	by	database/table	space/pl an
DBI 0=PX	Summarize l	by	pl an/database/t	able space

All the other summarization options of AUTHID, connect, buffer pool, location, and time are also available.

Print Workload Reports

Chapter 6. Using RxD2 with MAINVIEW for DB2

In this practice session, you

- $1. \ Learn\ how\ to\ use\ RxD2/FlexTools\ with\ MAINVIEW\ for\ DB2\ for\ SQL\ prototyping.$
- 2. Access DB2 Catalog and PLAN_TABLE information or invoke EXPLAIN directly from your terminal session for either local or remote DB2 systems (remote access is through DDF connections from a local DB2).

This practice session takes approximately one hour to complete.

Improve Performance with SQL Prototyping

SQL prototyping can be a valuable tuning exercise at two different times in the development cycle:

- When an application is first being developed and the basic performance characteristics of the SQL statements need to be validated against the design criteria.
- When a poorly performing SQL statement has been identified in an application and improvements are being sought.

RxD2 FlexTools provides a simple method both to execute and EXPLAIN SQL statements directly from the program source. There are often several possible methods to code an SQL statement, and the trick is to find the one with the best performance characteristics. Modifying and executing these variations while running a detail trace can simplify this task and document the results for you.

Begin by ensuring that RxD2 is accessible from your terminal session:

You can access RxD2 only from a terminal session running under ISPF or MAINVIEW Alternate Access. Also, to run this scenario, your terminal session must be on the same MVS system as your source libraries and the DB2 system.

1. Go to the MAINVIEW for DB2 Primary Option Menu.

You will see an RX option in the middle of the panel if RxD2 is installed.

2. Request this option:

```
OPTI ON ===> RX
                       RxD2 FlexTools
```

The RxD2 Primary Option Menu is displayed, as shown in Figure 96.

RX Is Available

1	oftware n ===>	Primary Option	Menu RxD2 FlexTools 2.1 Target ===> DB2G Userid BOLMXW2
	D	B2 Resource Adm	inistration
1	Pl ans	9	Storage Groups
2	Packages	10	RLF
3	Tabl es	11	DDF
4	Table Spaces	12	Synonyms
5	Parti ti ons	13	SYSCOPY
6	Indexes	14	Authorization by User
7	Index Partitions	15	Authorization by Resource
8	Databases	16	Stored Procedures
	pplication Functions	Gener	al Facilities
	Execute SQL	С	DB2 Commands
A2	DDLGEN for Tables	D	Defaults
A3	EXPLAIN PLAN_TABLE	T	Tutorial
A4	EXPLAIN SQL from Edit	(EXPL) N	What's New
A5	Execute SQL from Edit	(TEX) X	Exi t

Figure 96. RxD2 Primary Option Menu

3. Press **PF3** to return to MAINVIEW for DB2.

When RxD2 is installed, you will also see a short message RX AVAI LABLE at the top right of many other displays.

Start a Trace

To set up the trace for your tests:

1. Start a detail trace qualified by your AUTHID.

The default for a detail trace includes an SQL trace, which is usually sufficient information. If you also need to analyze data access by table space, you may want to add SCANS or I/O. Include LOCKS only for specific lock analysis, since this is very expensive. Log the trace so you can print reports later if desired.

If you have any questions about starting a trace request, go back through the first part of the practice session in Chapter 4, "Tuning an Application with Trace" on page 59.

2. Check that the trace has started correctly.

Press Enter until your trace request appears in the list and shows as active.

Test a Statement

To start testing:

1. From the Primary Option Menu, or any command line, select RxD2.

```
OPTION ===> RX
                          RxD2 FlexTools
  or
  COMMAND ===> RX
                          RxD2 FlexTools
2. Enter ISPF/PDF Edit.
```

3. Select your program source file and member in the normal way, and then locate the statement you want to test.

(If you have the DB2 IVP installed, you can use the DSNSAMP member DSN8MCA and choose the first statement.) (Use FIND 'EXEC SQL'.)

Execute SQL from Edit (TEX)

4. Choose the statement for execution.

```
COMMAND ===> TEX
```

OPTION ===> A5

Place the cursor on the statement text and press **Enter**.

If you execute this from a library with an unknown source type (for example DSNSAMP), you are asked to define whether the text is in COBOL, PL/I, and so on. Otherwise, the statement is parsed immediately and primed in a panel to prepare for execution, as shown in Figure 97.

Initiate Execution

```
BMC Software ----- Execute
                                            SOI. -----
Command ===>
                                                       TARGET ===> DB2G
Locati on
                  ===> DB2G
Maximum Fetches ===> 99999
Defaul\,t\,\,SQL\,\,Acti\,on\,\,===>\,\,COM\!M\!I\,T
                                  (COMMIT, ROLLBACK)
Current SQLID
                ===> BOLMXW3
Enter the SQL statement below, and press \ensuremath{\mathsf{ENTER}} to execute:
SELECT CREATOR, NAME, TYPE, DBNAME, TSNAME FROM SYSIBM SYSTABLES ORDER BY CREAT
R, NAME
```

Figure 97. Execute SQL Panel

5. Determine the maximum number of FETCHes that should be executed.

```
MAXI MUM FETCHES ==> 20
```

The default is 20. If you change it here, it affects only this one execution. You also can change the default in the Defaults option (RxD2/FlexTools Primary Option Menu).

6. Define whether you want to COMMIT or ROLLBACK.

```
DEFAULT SQL ACTION ==> COMMIT
```

The default is COMMIT. In both cases, the thread is terminated at completion so that an accounting record is cut for each execution.

7. Modify the SQL text if necessary.

Review and modify the SQL statement text before execution as dynamic SQL. Host variables are not supported (they are replaced by question marks in the text), so you may have to edit in appropriate values for the test. You also can delete or add clauses. It is not necessary to edit out blanks. The text will be flowed together for execution.

- 8. Change the current SQLID if necessary to qualify a table name or edit it into the text.
- 9. Press **Enter** to submit the SQL statement for execution.

Output is returned in a scrollable display, each row separated by asterisks and the row number, followed by one line per column, as shown in Figure 98.

Results of Execution

```
BMC Software ----- Execute SQL Output --- Row 145 to 180 of 1,174
Command ===>
                                                       SCROLL ===> CSR
                                                       TARGET ---- DB2G
Location \quad . \quad . \quad . \quad . \quad . \quad BB2G
ROW # 25 ************ 5 COLUMNS
ROW # 25
CREATOR = BOLMXW2
NAME = MWTTBLA
TYPE = T
DBNAME = MWDBTEST
TSNAME = MUTSPCA
ROW # 26 *********** 5 COLUMNS
CREATOR = BOLMXW2
TYPE = MWDBTEST

DBNAME = MWDBTEST

TSNAME = MWDBTEST
ROW # 27 ************ 5 COLUMNS
CREATOR = BOLMXW2
NAME = MANALE
TYPE = T
DBNAME = MMDBTEST
TEMAME = MUTSPC3I
ROW # 28 *********** 5 COLUMNS
CREATOR = BOLMXW2
NAME
                   = MWTTBL3J
TYPE
                   = T
             MWDBTESTMUTSPC3J
DBNAME
TSNAME
ROW # 29 ************ 5 COLUMNS
           = BOLMXW2
= MWTTBL3X
CREATOR
NAME
TYPE
                  = T
DBNAME
              = MWDBTEST
TSNAME
                   = MUTSPC3X
ROW # 30 *********** 5 COLUMNS
CREATOR = BOLMXW2
NAME
                  = MWTTBL3Z
TYPE
                   = T
DBNAME
                   = DSNDB04
TSNAME
                   = H3TTBL1
```

Figure 98. Execute SQL Output Panel

- 10. Repeat the modification and execution of the statement for as many iterations as you need.
- 11. Press **PF3** to return to your edit session.

If you wish, you can now choose another SQL statement to test.

EXPLAIN a Statement

You can EXPLAIN any statement while in edit. This can be very useful when you are first creating an SQL statement. You do not need to EXPLAIN every iteration you are testing now, since the MAINVIEW for DB2 trace captures the EXPLAIN data created for the dynamic SQL. Choose one to try out now so you know how it works:

1. Choose the statement for execution.

```
COMMAND ===> EXPL
```

Place the cursor on the statement text and press **Enter**.

You may be asked to define the source type, just as for TEX. Then the statement is parsed and primed in a panel to prepare for EXPLAIN, as shown in Figure 99.

You must have a PLAN_TABLE allocated for your AUTHID or, if changed, the Note: current SQLID.

Initiate **EXPLAIN**

```
BMC Software ----- EXPLAIN -----
Command ===>
                                             TARGET ===> DB2G
(Plan_Table must exist for this SQLID)
Enter the query number to use ===> 601
SQL statement to be explained:
SELECT DSN8410. DEPT. DEPTNO, DEPTNAME, MGRNO, PROJNO, PROJNAME FROM DSN8410. DEPT
FULL OUTER JOIN DSN8410. PROJ ON DSN8410. DEPT. DEPTNO = DSN8410. PROJ. DEPTNO
```

Figure 99. EXPLAIN PLAN_TABLE Qualifier Panel

2. Specify the query number to identify this iteration.

Type the query number to use ==> 1

The default is 1.

Review / modify the SQL statement text before EXPLAINing it. Host variables are replaced with parameter markers (questions marks) in a format acceptable to EXPLAIN. 3. Press **Enter** to submit the SQL statement to be EXPLAINed.

The EXPLAIN output is returned in a formatted, scrollable display, as shown in Figure 100.

Results of **EXPLAIN**

```
BMC Software ----- EXPLAIN PLAN_TABLE ----- Row 1 to 2 of 2
                                                      SCROLL ===> CSR
Command ===>
                                                       TARGET ---- DB2G
Catalog Prefix ===> SYSIBM
Location ===> DB2G
PLAN_TABLE . . . . : BOLMXW. PLAN_TABLE
Commands: SORT (Q, PL, PK, CO, DT)
LC CMDS: P (plan detail) T (table detail)
PK (package detail) X (index detail)
M (more detail)
         M (more detail)
LC QNO STP BLK MXSEQ PLAN PGM COLLECTION
.. .... ... ... ... .... ..... ......
    601 1 1 0 RXSEL1M RXD2
                                                            20010317 14491881
  Method: First Table Accessed
Access: Sequential Scan Prefetch: Sec
Tslock: IS Access Seq(Tabno): 1
Table: DSN8410. DEPT Correlation:
Index: Matching 0 Keys
Sort-New Table: None Composite: None
                                               Prefetch: Sequential
601 2 1 0 RXSEL1M RXD2 20010317 14491881

Method: Merge Scan Join Access: Sequential Scan Prefetch: Sequential Tslock: IS Access Seq(Tabno): 2

Table: DSN8410. PROJ Correlation: Matching O Kove
                                                   20010317 14491881
```

Figure 100. EXPLAIN PLAN_TABLE Output Panel

- 4. Most of the important information is available on this first display, but you can use line command M to see more detail.
- 5. Use the line commands to quickly access information about the DB2 objects accessed.

```
LC
         (Line Command)
 T
         (for Table detail)
 X
         (for Index detail)
```

All table/index catalog information upon which DB2 bases its access path selection is easily found with these dialogs.

- 6. Repeat the modification and EXPLAIN of the statement for as many iterations as you need.
- 7. Press **PF3** to return to your edit session.

If you wish, you can now choose another SQL statement.

Compare Test Results

To find out which of the test SQL versions ran best:

- 1. From edit, press **PF3** several times to return to MAINVIEW for DB2.
- 2. Look at your trace data.

```
OPTI ON ===> 5
                     HI STORY
                                 Historical Trace Data Sets
If you logged the trace, locate your data set here (SORT US, then LOCATE userid).
If not, go to Option 4, Current Traces.
```

3. Select the trace for viewing.

```
LC
       (Li ne Command)
S
       (S to select the trace data)
```

The first display (LTRAC) lists one line for each test execution (and DB2 accounting record). You can see immediately which test executions had the best performance as measured by elapsed and CPU times, as well as number of GETPAGEs.

4. Select one line for further analysis by tabbing to that line and pressing **Enter**.

You now have the complete DB2 Accounting information at your finger tips (STRAC). This provides you with statistics on wait times, locking, buffer pool activity, and I/O.

- 5. To compare this data to that from another iteration, use **PF10** and **PF11** to move to previous or next accounting record displays, without returning to the LTRAC list.
- 6. Tab through the expand buttons and press **Enter** to view summaries of SQL statistics, scans, I/O, or locks by table space (if traced).
- 7. To identify which SQL statement text was executed for this test iteration, tab to the **DETAIL** expand button and press **Enter**.

You are now viewing a chronological list of detailed events that occurred in DB2 while processing this statement (DTRAC display).

For dynamic SQL, this provides you with critical data to help you relate the performance data in the trace with the test SQL you executed.

8. Tab to the **BIND-TEXT** event and press **Enter** to see the complete text of the SQL statement executed, as shown in Figure 101.

Complete Text

```
----- RX AVAI LABLE
PARM ==> I 0111256, SEQ=1, LEVEL=2
                                       ROW 1 OF 1 SCROLL=> CSR
START: 11: 17: 10 AUTH: BOLMXW2 PLAN: RXDB2 CORR: BOLMXW2
                                               CONN: DB2CALL
  EVENT AT ELAPSED CPU DETAIL
                              *TYPE=DYNAMIC TEXT=SELECT * FROM SY+
BI ND- TEXT
           14. 892
SELECT * FROM SYSIBM SYSPACKAGE WHERE NAME LIKE '%'
```

Figure 101. DTRAC BIND-TEXT Pop-Up Display

9. Press **PF3** to return to DTRAC.

10. Tab to the EXPLAIN event and press Enter to see the dynamic SQL EXPLAIN data, as shown in Figure 102.

EXPLAIN Data

```
BMC Software ----- RX AVAILABLE
SERV ==> DTRAC I NPUT 12: 43: 58 I NTVL=> 5 LOG=> N TGT==> DB2HSR PARM ==> MYLOCKS, SEQ=3, LEVEL=3 ROW 1 OF 18 SCROLL=> CSR
EXPAND: CATALOG
START: 12: 32: 57 AUTH: BOLSMR4 PLAN: RXDB2 CORR: BOLSMR4 CONN: DB2CALL
______
 EVENT AT ELAPSED CPU DETAIL
EXPLAIN 5. 173 *PLAN=RXDB2 COST(1. 4)
QUERY NUMBER: 115 EXPLAIN DATE. : 2001-03-19 12:33:0284
GROUP MEMBER: DB2H STATEMENT TYPE: SELECT
PROGRAM NAME: RXSEL1M COLLECTION ID. : RXD2
VERSION NAME:
WHEN_OPTIMIZ: AT BIND TIME USING DEFAULT VALUES
______
BLKNO: 1 SEQNO: 1 MXSEQNO: 0
METHOD: FIRST TABLE
ACCESS: INDEX SCAN
                                   PREFETCH: NONE
COL_FN:
PAGE RANGE SCAN: NO
TSLOCK: IS
                    CORRELATI ON:
MATCHI NG:
TABLE: DSN8710. EMP
BLKNO: 1 SEQNO: 1 MXSEQNO: 1
METHOD: FIRST TABLE
METHOD: FIRST TABLE
ACCESS: MULTINDEX/UNION INDEX ONLY PREFETCH: NONE
COL_FN:
PAGE RANGE SCAN: NO
TSLOCK: IS
TSLOCK: 1S
TABLE: DSN8710. EMP CORRELATION:
INDEX: DSN8710. XEMP1 MATCHING: 1 KEYS
```

Figure 102. DTRAC EXPLAIN Pop-Up Display for DB2 5.1 and Above

EXPLAIN Data

```
BMC Software ----- RX AVAILABLE
SERV ==> DTRAC INPUT 17: 31: 16 INTVL=> 3 LOG=> N TGT==> DB2G
                         ROW 1 OF 6 SCROLL=> CSR
PARM ==> I 0111256, SEQ=1, LEVEL=2
EXPAND: CATALOG
START: 11: 17: 10 AUTH: BOLMXW2 PLAN: RXDB2 CORR: BOLMXW2 CONN: DB2CALL
_____
 EVENT AT ELAPSED CPU DETAIL
          .....
EXPLAI N 19. 708 *PLAN=RXDB2 COST (4, 061. 4)
______

        QUERY NUMBER
        115
        TI MESTAMP
        1996-03-05
        11: 17: 1856

        GROUP MEMBER
        DB2G
        COLLECTI ON 1D
        RXD2

BLK SEQ DESCRIPTION
1 1 METHOD: FIRST TABLE
       ACCESS: SEQUENTIAL SCAN PREFETCH: SEQ
       TSLOCK: IS
                                             CREATOR: SYSI BM
       TABLE: SYSPACKAGE
       I NDEX:
                                             CREATOR:
       SORT:
             NONE
```

Figure 103. DTRAC EXPLAIN Pop-Up Display for DB2 4.1 and 3.1

Improve Performance with SQL Prototyping

If you need to review the catalog information, the EXPLAIN expand button takes you back to RxD2 to a display of the first table accessed.

11. If needed, tab to any SQL statement and press Enter to see the detail row statistics.

This can show you how many rows were accessed and whether the predicate was Stage 1 or 2.

- 12. Tab to the **LOCK SUMMARY** event to see an analysis of locking and lock states (tracing lock events is not necessary to get this).
- 13. As with STRAC, you can use PF10 and PF11 to move between the events produced by this test iteration.

Print Results

If you logged the trace, you may now want to print a report for desk analysis or a team SQL review:

- 1. Press **PF3** until you are back in the History Traces display.
- 2. Select the print option for your log data set.

L.C (Line Command) (for Print)

A panel on which you can define your print options is displayed. For more details, refer to "Print a Trace Report" on page 88.

Recommended print options for SQL prototyping are

LTRAC=Y One line identifier

STRAC=SUMMARY DB2 accounting record summary

Detail events DTRAC=Y

POPUP=(BIND-TEXT, EXPLAIN) SQL text and EXPLAIN data

You may want to add

NEWPAGE=TRAN Start a new page per test execution

LEVEL=3 To see all detail events

You may also want to print the detail summaries of STRAC in a separate report (they cannot be produced in the same report with DTRAC entries).

LTRAC=Y One line identifier

STRAC=ALL Complete accounting with detail summaries

Access DB2 Catalog and PLAN_TABLE Information

DB2 performance is dependent on three factors:

- How the DB2 system is configured (maximum threads, buffer pool, EDM pool, logging, and so on)
- The DB2 workload (SQL optimization, lock contention, I/O patterns, and service times, and so on)
- The DB2 objects themselves (tables, table spaces, indexes, plans) and the status information stored in the DB2 catalog about them

MAINVIEW for DB2 and other performance monitors mainly present data about the first two categories. Catalog and PLAN_TABLE access is usually a completely separate function. The ability to access RxD2/FlexTools directly from your BBI Terminal Session provides this information whenever you need it (subject to standard DB2 security).

Accessing the RxD2 Primary Option Menu

Access to DB2 data with RxD2 is provided from any MAINVIEW product that runs in full-screen mode, not just MAINVIEW for DB2. This includes

- AutoOPERATOR and FOCAL POINT—an operator or systems programmer can check the status of DB2 resources that may be affecting availability
- MAINVIEW for CICS—a CICS systems programmer or applications manager can investigate plans and tables used from CICS
- MAINVIEW for IMS—an IMS systems programmer or DBA can investigate plans and tables used from IMS

As described in the first session, the RxD2/FlexTools Primary Option Menu is available from most MAINVIEW applications running in full-screen mode.

From the MAINVIEW for DB2 Primary Option Menu:

From any command line:

From any MAINVIEW for DB2 or MAINVIEW for IMS service display:

$$SERV ===> RX$$

Now all the capabilities of RxD2 are available for use.

Accessing EXPLAIN for Currently Executing SQL

When a DB2 application is running too long, you may want to investigate the current SQL statement being executed. The MAINVIEW for DB2 detail user (DUSER) display provides hyperlink expand buttons to perform an EXPLAIN or access existing PLAN_TABLE EXPLAIN data.

To access EXPLAIN data for currently executing SQL:

- 1. Access the DUSER display:
 - a. Return to the Primary Option Menu.
 - b. Choose Option 2—ANALYZERS.
 - c. Line select **USERS** from the list of Analyzer Display Services.
 - d. Tab to an active thread and press **Enter** to access DUSER.

Check that there is an active SQL statement displayed, as shown in Figure 104.

Expand to EXPLAIN ==>

```
BMC Software ----- DETAIL USER STATUS
                                   ----- RX AVAI LABLE
SERV ==> DUSER
             INPUT 17: 32: 09 INTVL=> 3 LOG=> N TGT==> DB2G
PARM ==> MXW3
                               ROW 1 OF 96 SCROLL=> CSR
EXPAND: MON(USER), UTRAC, ST(START TRACE), LOCKE, EXPLAIN, PT
      ACCOUNTING: ENV, ELAPSED, SQLCOUNTS, BPOOL, LOCKS, PRLL, SPAS, DDF
RUNTI ME ANALYSI S IN DB2 IN APPL. TOTAL %IN DB2(=) TOTAL(*)
----- 0 ...25...50...75..100%
CPU TIME 64 ms
DB2 WAIT TIME 00: 09: 14
- - - - - ACTI VI TY - - - - -
                         - - - - KEY INDICATORS - - - - -
GETPAGES......243, 322
SYNC I/O (PRLL= 0) .....24, 225
PREFETCH......27, 644
UPDATES/COMMI T. . . . . . . . . . . . . 0. 0
BFR HIT RATIOS: . . . VP= 90%, HP= 0\%
193 STATEMENT TIFE. OF EACH CPU TIME: 1,897 ms ELAPSED TIME: 00:01:06
STATEMENT #:
ACTIVE IN DB2
Package/DBRM: DSNESM68 (DYNAMIC)
                             PLAN I SOLATION LEVEL: RR
PROCEDURE/UDF/TRI GGER: DSN8SPAS TEST
 SELECT DISTINCT TBCREATOR, TBNAME, NAME, COLTYPE, LENGTH, SCALE, NULLS, DEFAUL
T FROM SYSIBM SYSCOLUMNS C, SYSIBM SYSCOLAUTH CA, SYSIBM SYSTABAUTH TA WHERE C. T
BCREATOR = USER OR C. TBCREATOR = 'PUBLIC' OR (CA. GRANTEE = USER AND CA. TNAME = C
. TBNAME) OR (C. TBNAME = TA. TTNAME AND TA. GRANTEE = USER)
```

Current SQL Statement ==>

Figure 104. User Detail Status Display (DUSER)—Base Section

2. Select the **EXPLAIN** expand button.

A qualifier panel is displayed with the SQL text from DUSER.

If the DB2 target is on the same MVS as your terminal session, RxD2 accesses it directly (see the TARGET field). If the DB2 target is on a remote MVS, RxD2 accesses it through DDF. The TARGET name shown now is the local DB2 your RxD2 session is connected to (set in the Defaults panel) and LOCATION identifies the remote DB2.

3. If necessary, modify the query number and PLAN_TABLE owner (current SQLID).

```
Enter the query number to use ===> 1
Current SQLID
                             ===> your userid
```

Note: If your SQL has unqualified table names, you may need to set up special PLAN_TABLEs with the appropriate prefixes so that the current SQLID also can provide the proper table name qualifications.

4. Press **Enter** to invoke EXPLAIN, as shown in Figure 105.

EXPLAIN Output for Current SQL Statement

```
BMC Software ----- EXPLAIN PLAN_TABLE ----- Row 1 to 2 of 2
Command ===>
                                                     SCROLL ===> CSR
                                                     TARGET ---- DB2G
Catalog Prefix ===> SYSIBM
Location ===> DB2G
PLAN_TABLE . . . . : BOLMXW. PLAN_TABLE
Commands: SORT (Q, PL, PK, CO, DT)
        PK (plan detail)
PK (package detail)
M (more detail)
T (table detail)
X (index detail)
LC CMDS: P (plan detail)
LC QNO STP BLK MXSEQ PLAN PGM COLLECTION
                                                         DATE TI ME
-- ---- --- --- ----
    601 1 1 0 RXSEL1M RXD2
                                                         19951102 14491881
  Method: First Table Accessed
  Access: Sequential Scan
Tslock: IS
Table: DSN8410. DEPT
Index:
Sort-New Table: None

Prefetch: Ser
Access Seq(Tabno): 1
Correlation:
Matching 0 Keys
Composite: None
                                             Prefetch: Sequential
______
  Method: Merge Scan Join
Access: Sequential Scan
Tslock: IS
Table: DSN8410. PROJ
Index:
Sort-New Table: JOIN

RXSEL1M RXD2
Full Outer Join
Access Seq(Tabno): 2
Correlation:
Matching O Keys
Composite: JOIN
                                                  19951102 14491881
                                              Prefetch: Sequential
 ______
```

Figure 105. EXPLAIN PLAN_TABLE Output Panel

This option can be used for both static and dynamic SQL. However, for static SQL, the results may be different from the access path chosen by the DB2 Optimizer at BIND time.

- 5. Press **PF3** until you return to DUSER.
- 6. If this is a static SQL statement, select the **PT** expand button.

A qualifier panel is displayed primed with the query number (statement number) and program (DBRM or package).

7. Your user ID is primed as the PLAN_TABLE owner.

You may need to change this specification before proceeding.

8. Press **Enter** to view the PLAN_TABLE EXPLAIN data.

Accessing EXPLAIN from a Trace

The previous practice session, "Improve Performance with SQL Prototyping" on page 112, showed how both SQL text and EXPLAIN information is captured in a detail trace for dynamic SQL. Neither of these events is provided by DB2 for static SQL. However, direct hyperlinks to RxD2 provide equivalent information.

To access EXPLAIN data from a trace:

- 1. Access a detail trace that includes static SQL:
 - a. From the Primary Option Menu, choose Option 4—Current Traces (or Option 5—History Traces, if you prefer).
 - b. Line select the detail trace to view the LTRAC display of traced threads.
 - c. Tab to a trace entry with several SQL statements and press Enter to see the accounting data for that thread (STRAC display).

2. Select the SQL Summary section by tabbing to the SQL button in the SUMMARIES EXPAND line and pressing **Enter**.

A summary of all SQL executed by that thread is displayed, as shown in Figure 106.

SQL**Summary**

EXPAND:	MON (W	KLD), D	, SQL, SORT: ETALL, HIS	STORY				ROW 1				
			ENV, ELAPS QL, SCANS,				POOL,	LOCKS,	PRLL,	PKG,	SPAS,	DDF
			- SQL SU	MMARY (DETAI L	TRA	CE ONL	LY)				
STMT					AVG.			SORT	PA	AGES S	SCANNEI)
TYPE	STMT	COUNT	ELAPSED								WORK	
SELECT	3228	1	25 ms		1, 930		0. 3	0	2		0	0
SELECT	3347	2	11 ms	2. 4	4, 047	us	1. 5	0	11	4	0	0
OPEN	3565	6	172 us	0. 1	170	us	0. 2	0	0	0	0	0
FETCH	3578	11	1,986 us	2. 3	782	us	1.6	0	19	3	0	0
CL0SE	3664	6	192 us	0. 1	149	us	0. 2	0	0	0	0	0
SELECT	3671		1,776 us		1, 091	us	1. 2	0	12	0	0	0
SELECT	3283	1	2,643 us	0.3	1, 888	us	0.3	0	1	0	0	0
OPEN	3299	1 2	109 us	0.0	107	us	0.0	0	0	0	0	0
FETCH	3313	2	907 us	0. 2	855	us	0.3	0	1	0	0	0
CLOSE	3334	1	142 us	0.0	141	us	0.0	0	0	0	0	0
OPEN	3456	1 5	693 ms	74. 1	414	ms	74. 9	8	23	1187	2	0
FETCH	3468	5	440 us		322	us	0.3	0	0	0	6	0
SELECT	4803	1	1, 269 us	0. 1	1, 121	us	0. 2	0	2	0	0	0
PGM: PO2	25D100	44		83. 9			81. 0	8	71	1195	8	0
SELECT	1239	1	1,040 us	0. 1	1, 040	us	0. 2	0	2	1	0	0
OPEN	1263	1	66 ms	7. 1	47	ms	8. 6	172	13	6	9	0
FETCH	1273	87	201 us	1. 9	177	us	2.8	0	0	0	2	0
CLOSE	1324	1	250 us	0.0	250	us	0.0	0	0	0	0	0
OPEN	1333	1	15 ms	1.6	14	ms	2. 6	7	6	4	5	0
FETCH	1343	5	254 us		254	us	0. 2	0	0	0	2	0
SELECT	1375	3	1,746 us	0.6			0.6	0	0	12	0	0
CL0SE	1393		126 us	0.0	126	us	0.0	0	0	0	0	0
PGM: PO2	25D200	100		11. 4			15. 0	179	21	23	18	0
SELECT	389	1	38 ms	4. 2	18	ms	3. 4	0	10	3	0	0
OPEN	482	1	135 us	0.0	134	us	0.0	0	0	0	0	0
FETCH	489	10	459 us	0. 5	302	us	0. 5	0	1	0	0	0
PGM: PO2	25D300	12		4. 7			3. 9	0	11	3	0	0
** TOTAL	S ***	156						187	103	1221	26	0

Figure 106. SQL Summary (STRAC)

3. Select one of the static SQL statements to view the execution statistics for that SQL statement, as shown in Figure 107.

SQL**Statistics**

BMC Software DETAIL TR. SERV ==> STRAC INPUT 10: 2: PARM ==> TEST3, SEQ=000017, SQL EXPAND: SQLTEXT(EXPLAIN)		OG=> N TG	T==> DB2G
STATEMENT: 350 SELECT	NUMBE	R OF EXECU	TIONS: 2
	APSED: AVERAGE 2,	794 us T	OTAL 5. 588 us
			OTAL 2, 543 us
LOCATION: DB1D			
PACKAGE: SAJUYH2I		AVERAGES	
	I NDEX	SEQ- DATA	SEQ- WORK
ROWS PROCESSED ALL TYPES	4	2	0
ROWS PROCESSED CORRECT TYPE	4	2	0
ROWS QUALIFIED BY DM (STAGE	1) 3	0	0
ROWS QUALIFIED BY RDS (STAGE		0	0
ROWS INSERTED	0	0	0
ROWS UPDATED	0	0	0
ROWS DELETED	0	0	0
PAGES SCANNED	8	2	0
REFERENTI AL INTEGRITY PROCESS	NG:		
PAGES SCANNED	0	0	0
ROWS DELETED/SET NULL	0	0	0

Figure 107. SQL Statement Pop-Up Display (STRAC)

4. Tab to the **SQLTEXT(EXPLAIN**) expand button and press **Enter**.

If this statement is not static SQL, the button is not highlighted. Try another statement.

This displays the complete static SQL statement text from the appropriate plan or package catalog table. From this panel, you can choose to

Access existing EXPLAIN data in a PLAN_TABLE

Your user ID is primed as the PLAN_TABLE owner. You can change it before making the request.

EXPLAIN the text and access the RxD2 EXPLAIN display for the statement (although this may not show the access path actually used that was chosen at BIND time)

A qualifier panel is first displayed primed with the SQL text and query number 1. Your user ID is primed as the PLAN_TABLE owner. You can change these specifications before executing the EXPLAIN. If any host variables are in the statement, they are replaced by parameter markers (question marks) to make it EXPLAINable.

Execute the statement

You can specify the maximum number of fetches, whether to COMMIT or ROLLBACK, and change the SQLID if necessary before execution.

If any host variables are in the statement, they are replaced by question marks, and the text is presented on the Execute SQL panel to allow for tailoring into an executable format.

The same panels you have viewed previously for the RxD2 EXPLAIN are shown. Note:

- 5. Press **PF3** to return to STRAC.
- 6. Select the **DETAIL** expand button to view the detail events that occurred within the life of the thread, as shown in Figure 108.

Detail **Events**

SERV ==> 1 PARM ==> 7 EXPAND: 1 START: 09:	DTRAC FEST3, LI NESE 17: 11	SEQ=0000; L(DETAIL) AUTH: JI	I NPUT 17, LEVEL), HI STO EK1	10: 2: = 2 RY PLAN: DS	1: 48 SNT	8 INT	VL=> ROW ORR:	3 L0 1 DB22	OG=> N TGT== OF 35 SCR	> DB2G OLL=>	CSR H
EVENT		AT	ELAPSED	CPI	IJ	DETAI	L				
CREATE- THI)	0. 000	45 m	s 4, 492	us						
PLAN- ALLO							ATI 0	N=CS	ACQ=USE REL	=COMMI	T
PKG- ALLOC		0.065				*DSNE	SPCS	I S0=0	ACQ=USE REL CS ACQ=USE	REL=CO	MI T
PREPARE	350	0.069	1,361 m	s 26	ms	*RC(0)	C=DT	D/X	PS(10)
BI ND- TEXT	Γ	0.070				*TYPE	=DYN	AMI C	TEXT=SELECT COST(4.6)	* FROM	DS+
EXPLAI N									COST(4. 6)		
EDM- REQ											
OPEN						•					
				s 6, 247	us				D/X	PS(2)
OPEN- TS									S=DSN8S21D		
									S=XDEPT3		
FETCH	532		35 m				- /				
	532					,			D/X		
	532					,			D/X		
FETCH	532					,			D/X		
	532					•			D/X		
	532		386 u			- (- /		D/X		
FETCH	532	3. 673	337 u	s 337	us	*RC(0)	C=DT	D/X		

Figure 108. Detail Trace Events (DTRAC)

7. Scroll down with PF8 until you see a static SQL statement and select it to view the SQL statement pop-up display.

This looks much like the one you saw from the SQL Summary, but is only for one execution of that statement.

The same SQLTEXT(EXPLAIN) expand button is available here.

8. Press **PF3** until you return to the Primary Option Menu.

Accessing Other Catalog Data with Direct Hyperlinks

Analyzer displays of DB2 database objects (DBATs and DBTS), as well as the detail trace dynamic SQL EXPLAIN pop-up display, provide direct hyperlinks to the related catalog information on selected objects.

To hyperlink directly to related catalog data:

- 1. From the Primary Option Menu, select Option 7—I/O Analysis and then select Option 1— I/O by DB/TS.
- 2. Line select one of the table spaces.

DBIOD—I/O Analysis by Data Set is displayed and the parameter field is primed with the name of the selected database and table space, as shown in Figure 109.

Selected **Object**

```
BMC Software ----- I/O Analysis-Dataset
                                         -----
                                                       RX AVAI LABLE
SERV ==> DBI OD
                     I NPUT
                           18: 33: 03 INTVL=> 3 LOG=> N TGT==> DB2G
 \mbox{PARM} ==> \mbox{TOTAL, SO=TS, } \mbox{DBTS=(DSN8D41A, DSN8S41E)} \qquad \mbox{LI NE} \qquad 1 \ \mbox{OF} \qquad 4 \ \mbox{SCROLL=> CSR} 
EXPAND: I /0- DB/TS, I /0- BP00L, I /0- VOL, LI NESEL(DBTS), CATALOG
OPTION: TOTAL, SYNC, ASYNC, CACHE
                     I/0 I/0 MAX
DATA
       TABLE
              DS/
                                      AVG
                     COUNT % I OWAIT I OWAIT
       SPACE PRT
BASE
5 17. 9
9 32. 1
                                36
48
                                        25 | *****
DSN8D41A DSN8S41E 003
                                       16 | ****
DSN8D41A DSN8S41E 001
DSN8D41A DSN8S41E 002 7 25.0 112
                                      45 | ********
      ******************* END OF DATA ***************
```

Figure 109. I/O Analysis by Data Set (DBIOD)

3. Select the CATALOG expand button to access a primed DB2 Table Space Administration qualifier panel; then press **Enter** to display catalog information for the selected table space, as shown in Figure 110.

Table Space Catalog Data

```
BMC Software ----- Show Table Space ----- Row 1 to 1 of 1
Command ===>
                                                  SCROLL ===> PAGE
                                                  TARGET ---- DB2G
Locati on
               ===> DB2G
Catalog Prefix ===> DB2G. SYSIBM
Commands: SORT (DB, TS, column no.)
                                     GU (Group Utility generator)
                                     Q (generate QUIESCE JCL)
LC CMDS: A (authorization)
         C (generate COPY JCL)
                                    R (generate REORG JCL)
                                   RC (generate REORG and COPY JCL)
         D (drop table space)
         KD (generate CHECK DATA JCL) S (show partitions)
         KX (generate CHECK INDEX JCL) T (generate RUNSTATS JCL)
         L (list tables within) Y (SYSCOPY recovery info)
LC
  DSN8S41E Status: AVAILABLE
      Database: DSN8D41A Segment Size: 0
                                                 Lock Rule: PAGE
      Creator:
                  BOLBPL1 Page Size(K): 4
                                                 Erase Rule: N
      Partitions: 4
                                        BPO
                                                 Close Rule: N
                            Usi ng:
                           Active Pages: 120
      Tabl es:
      Statstime: 1996-02-01-11.05.32.584702
                                                 Space: OKB
```

Figure 110. Table Space Catalog Display

From this display, you can use the line commands to browse all the other related catalog information for tables (L), partitions (S), indexes (per table), and so forth.

- 4. Press PF3 until you are back at the DBIOR display.
- 5. Select the **CATALOG** expand button again.

Here there are no selected objects. The table space qualifier panel is presented so you can choose which table space or group of table spaces you want to view, as shown in Figure 111.

Specify Qualifiers

```
BMC Software ----- DB2 Table Space Administration -----
                                                      TARGET ===> DB2G
Command ===>
Locati on
                ===> DBOG
Catalog Prefix ===> SYSIBM
Catalog Table . . . : SYSIBM SYSTABLESPACE
Specify at least one table space qualifier.
                     Qualifier (e. g. NULL, ^-='AB', >123, AB++CD*)
* DBNAME
               ===> DSN*
  TSNAME
               ===>
  CREATOR
               ===>
  DBI D
               --->
  OBI D
                              (Buffer Pool ID)
  BP00L
                ===>
 PARTI TI ONS
 LOCKRULE
               ===>
                              (A-any, P-page, T-table, S-tablespace, R-row)
 ERASERULE
                              (Y. N)
               ===>
  CLOSERULE
                              (Y, N)
                              (A-available, C-check pending, I-incomplete)
 STATUS
  TABLES
  ACTI VE PAGES --->
                    Press ENTER to process, END to exit
```

Figure 111. Table Space Qualifier Panel

For example, in the DBNAME field, type **DSN*** to display all system table spaces.

When you are finished with this exercise, press PF3 several times to exit the EXPLAIN function. You can initiate the next exercise from any MAINVIEW for DB2 service.

Accessing Specific Objects in the Catalog

At other times, you may need information about a specific DB2 object or user that is being shown on a display of one of the BBI products. For example, you might be on a tabular display like LTRAC where a direct hyperlink is not available. Instead of writing the name down on a piece of paper to later type in a selection panel, the BBI—RxD2 interface provides subcommands that prompt you for immediate entry of the object name. If you decide not to type the name, you are presented with a qualifier panel that allows you to select a list of these objects.

To view details about a specific plan:

1. Type

COMMAND ===> **RX PL planname**

If you are in a display with a COMMAND line (for example, when viewing a DB2 message in the Log Display), you can type the plan name directly after PL on the COMMAND line.

If you are in a display with a SERV line, just type **RX PL** and press **Enter**. You are prompted at the bottom of the screen for the plan name (for example, in the STRAC trace display).

2. Press **Enter** to go to RxD2.

The TARGET is set to the local DB2 from your Defaults panel.

To access a different DB2 system on the same MVS as your terminal session, specify the correct target name on the qualifier panel. To access a remote DB2 system (if connected with DDF), keep the TARGET pointing to any local DB2 and specify the location name of the remote DB2. You also can change the catalog prefix to view an alternate catalog.

3. If you specify a plan name, RxD2 displays the DB2 Plan Administration panel with one line of information about that plan, as shown in Figure 112.

Information for One Plan

```
BMC Software ----- DB2 Plan Administration ----- Row 1 to 1 of 1
Command ===>
                                               SCROLL ===> CSR
                                               TARGET ---- DB2G
            ===> NEW YORK
Catalog Prefix ===> SYSIBM
COMMANDS: SORT (column no.)
        A (plan authorization) F (free plan)
B (bind plan functions) P (show plan detail)
C (list plan collections) R (rebind plan)
D (show plan dependencies) S (show DBRMs and SQL statements)
LC CMDS: A (plan authorization)
                                  F (free plan)
          - STATUS- -
                                  ---- BIND ----- BIND OPTIONS ----
LC PLANNAME VALD OPER CREATOR BOUND BY DATE TIME ISOL VALD ACQ REL
DSNST01 Y Y BOLSMR2 BOLSMR2 950817 15353898 CS DFER USE COMMIT
```

Figure 112. DB2 Plan Administration Panel

All the line commands are available to access more detailed information.

```
LC
       (Line Command)
       (to show plan authorizations)
 C
       (to list plan collections)
 D
       (to show plan dependencies)
 P
       (to show plan detail)
 S
       (to show DBRMs and SQL statements)
```

For example, you may need to see the plan dependencies or authorizations to find out why an application isn't running.

The plan detail and static SQL statement text are valuable when analyzing a detail trace for application tuning.

4. To view the EXPLAIN results for a specific plan:

```
COMMAND ===> RX PT planname (owner)
```

If you don't enter the operands, you are prompted at the bottom of the screen. You can specify the PLAN_TABLE owner, or default to your user ID.

The EXPLAIN results are displayed on a panel from which catalog data about the accessed tables and indexes can be accessed directly.

```
LC
       (Line Command)
P
       (to show plan detail)
T
       (to show table detail)
       (to show index detail)
```

For example, use this command when investigating a production plan that has been showing up in exception reports with increased run times. All the dependencies and statistics are available starting from this one screen, as shown in Figure 113.

EXPLAIN Results for One Plan

```
BMC Software ----- EXPLAIN PLAN_TABLE ----- Row 1 to 2 of 2
Command ===>
                                                              SCROLL ===> CSR
                                                              TARGET ---- DB2G
Catalog Prefix ===> SYSIBM
Location ===> DB2G
PLAN_TABLE . . . . : BOLMXW. PLAN_TABLE
Commands: SORT (Q, PL, PK, CO, DT)
          P (plan detail)

PK (package detail)

X (index detail)
LC CMDS: P (plan detail)
M (more detail)
LC QNO STP BLK MXSEQ PLAN PGM COLLECTION DATE
                                                                              TI ME
                                   -----
-- ---- --- --- ----
                                                                    -----
    601 1 1 0 RXSEL1M RXD2 20010317 14491881
   Method: First Table Accessed
   Access: Sequential Scan
                                                       Prefetch: Sequential
                             Access Seq(Tabno): 1
Correlation:
Matching 0 Keys
   Tslock: IS
   Table: DSN8410. DEPT
   Index:
                                              Composite: None
   Sort-New Table: None

        601
        2
        1
        0
        RXSEL1M RXD2

        Method:
        Merge Scan Join
        Full Outer Join

        Access:
        Sequential Scan
        Prefetch:

        Tsl ock:
        IS
        Access Seq(Tabno):

        Tabl e:
        DSN8410. PROJ
        Correlation:

        Index:
        Matching 0 Keys

        Sort-New Tabl e:
        JOIN
        Composite:

                                                                    20010317 14491881
                                                       Prefetch: Sequential
                                          Access Seq(Tabno): 2
   Sort-New Table: JOIN
                                            Composite: JOIN
______
```

Figure 113. EXPLAIN PLAN_TABLE Output Panel

5. To view the details about a specific table:

```
COMMAND ===> RX TB tablename | OBID
```

If you don't enter the operand, you are prompted at the bottom of the screen. You can specify either the table name or OBID.

6. If you specify a table name, RxD2 displays the Show Table Objects panel, as shown in Figure 114.

Information for One Table

```
BMC Software ----- Show Table Objects -----
Command ===>
                                     TARGET ---- DB2G
Catalog Prefix ===> DB2G. SYSIBM
Location . . . . :
Name . . . . . . : SYSIBM SYSTABLES
Type . . . . . : TABLE
LC CMDS: S (show detail)
  COLUMNS
           Columns In TABLE 39
______
  TABLESPACE Tablespace: DSNDB06. SYSDBASE Rows: 300 Pages: 300 TS Pct: 75%
INDEXES Indexes Defined For This TABLE 2
Primary Key Columns: 2
 RELATIONS Referential Integrity Relationships
Parent: 1 CHILD:
Check: OK
 CHECKS Check Constraints: 0
_____
 DEPENDENCIES Plans Depending On This TABLE
           Audit: NONE Edproc: Validproc:
             Statstime: 0001-01-01-00.00.00.00.000000
             Compressed: -1%
```

Figure 114. Show Table Objects Panel

The S line command is available to access more detailed information. It provides access to related table space, column, index, key, referential constraint, or plan dependency data.

7. To view the details about a specific index:

```
COMMAND ===> RX IX indexname | OBID
```

If you don't enter the operand, you are prompted at the bottom of the screen. You can specify either the index name or OBID.

8. If you specify an index name, RxD2 displays the Show Index panel, as shown in Figure 115.

Information for One Index

```
BMC Software ----- Show Index ----- Row 1 to 1 of 1
Command ===>
                                                                                                               SCROLL ===> CSR
                                                                                                               TARGET ---- DB2G
Catalog Prefix ===> DBOG. SYSIBM
Location \quad . \quad . \quad . \quad . \quad : \quad DBOG
Commands: SORT (IX,TB) GU (Group Utility generator)
LC CMDS: D (drop index) C (generate CHECK INDEX JCL)
I (show index parts) R (generate REORG JCL)
K (show index key columns) T (generate RUNSTATS JCL)
Commands: SORT (IX, TB)
                                                                                  GU (Group Utility generator)
LC
     SYSIBM DSNDTX01 *** RUNSTATS RECOMMENDED *** DBI D: 6
Created As: Pri mary On Table: SYSIBM SYSTABLES OBI D: 61
Subpages: 1 Cluster Uni que First Keys: -1
Bufferpool: BPO Defined: N Uni que Full Keys: -1
Close: N Status: N Levels of Index: -1
Key Columns: 2 Ratio: 0% Leaf Pages: -1
Type: 2 Statstime: 0001-01-01-00.00.00.0000000
```

Figure 115. Show Index Panel

All the line commands are available to access more detailed information.

- LC (Line Command)
- Ι (to show index parts)
- K (to show index key columns)

Chapter 7. Printing Reports

These scenarios teach you how to print both your online and offline reports.

In this practice session, you

- 1. Print an online history trace and export an online windows-mode view for offline review.
- 2. Print offline traces from a trace log data set or SMF records.
- 3. Print offline Performance Reporter reports from both SMF data and DB2 tables.

This practice session takes approximately one hour to complete.

Print Online Reports

You can both print online history traces and export online windows-mode views for offline

History Traces (Thread Data)

In previous exercises, you learned how to run a trace and view it online. However, depending on the results, you may want to have a hardcopy for further analysis. Batch reports can also be valuable tools during an application review meeting.

Note: This section describes printing a trace, but you may also want to look at the accounting reports produced from SMF data, either from DB2 tables or directly from the extracted DB2 accounting records. See "Performance Reporter Reports" on page 148 and the MAINVIEW for DB2 Performance Reporter User Guide for more information.

To begin this exercise:

1. From the Primary Option Menu, select the **HISTORY TRACES** option.

```
OPTI ON ===> 5
```

This panel not only provides access to view the trace data online but also offers several line commands to simplify management of the trace log data sets:

- Show the options used for this trace
- P Generate the JCL to print a batch report
- D Delete this data set from the trace directory
- \mathbf{E} Reset the log data set for reuse
- V Verify that the directory entry matches the data set contents
- Ν Add a new data set to the directory (moved from another system)
- A Archive the data set (only if an archive started task was specified)
- Free a data set currently being read

Usually you will need only W(SHOW), D(DELETE), and P(PRINT). We are going to concentrate now on P. You can try the others when you need those functions.

All Data per Traced Thread

To print a trace report showing all data per traced thread:

1. The history traces display shows the most recent traces at the top, but you can sort on any column and use the locate command to help you find other trace logs. For example, you can sort on userid to group all your own trace logs together.

Now, select your trace log data set for print.

```
LC
         (Line Command)
 P
         (for PRINT)
```

The Batch Trace Print panel is displayed, as shown in Figure 116, where you can specify options to print a batch report.

Printing a Trace

```
BMC Software ----- BATCH TRACE PRINT ----- PERFORMANCE MGMT
COMMAND ===>
                                                             TIME --- 15:00
Update j ob ==> N (Y/N - update j ob statement)
                                                           (END to edit JCL)
Title line 1 ==>
Title line 2 ==>
Data Selection:
From date \Rightarrow 16MAR2001 Time \Rightarrow 1125
To date ==> 17MAR2001 Time ==> 1412
  PLAN
  AUTHI D ==>
   CONNECT ==>
  CORR
           ==>
   LOC
  DB2PKG ==>
REPORT SELECTION:
  LTRAC ==> NO
                                       (YES/NO)
   STRAC ==> NO
                                       (NO, ALL, SUMMARY, section1, section2..)
  DTRAC ==> NO
                                       (YES/NO)
  POPUP ==> NO
                                       (NO/ALL/SQL/event1, event2, . . . )
                   (A/C/L/P/T)
   TSUM ==>
                                       SORT ==> (for any TSUMx)
  TSTAT ==> NO
                    (SUMMARY/ALL/NO)
                                       INTERVAL ==> 1H (for TSUMT only)
   DBI 0 ==>
                     (X/A/C/F/L/P/T/xx) IOSORT ==>
                                                          (for any DBIOx)
                                       IOINTVL ==> 10M (for DBIOT only)
```

Figure 116. Batch Trace Print Panel

2. If this is your first time using this option, you must update your job statements.

```
Update Job ==> Y
```

3. Press **Enter** to display a job statement data entry panel.

Fill in the required information and return using **PF3**.

- 4. Set the Update Job option to N.
- 5. Fill in the options for a report.

```
TITLE1 ==> any title
                       Optional. Centered in first report header.
TITLE2 ==> any title
                       Optional. Centered in second report header.
```

Data Selection is optional. The selection fields can be used to reduce the amount printed from a long trace.

Data Selection:

```
From date ==> ddmmnyyyy
                         Ti me ==> hhmm
    date ==> ddmmyyyy
                        Ti me ==> hhmm
```

The date and time fields are primed with the start and end date-time of the trace. You can modify them to select a shorter time period.

```
PLAN
         ==> plan name
AUTHI D
        ==> authorization id
CONNECT ==> connection name
CORR
         ==> correlation id
LOC
         ==> location name
DB2PKG
        ==> db2 package name
```

The Data Selection identifiers allow you to select only a subset of threads that you need to analyze further, such as one particular plan from a Thread History (THRDHIST) trace.

```
REPORT SELECTION:
```

```
LTRAC
       ==> N
STRAC
      ==> ALL
                            Print data per thread traced.
DTRAC
      ==> N
POPUP
       ==> N
TSUM
       ==>
TSTAT
       ==> N
DBI 0
```

There are many different reports that can be generated, either singly or combined. See "Batch Trace Print" on page 143 for some examples. Browse "Printing a Trace" in Volume 3 of the MAINVIEW for DB2 User Guide for a full explanation of the options and to see sample reports.

The reports are based on printouts of the online displays, so the options are selected using the names of these displays, like LTRAC, STRAC, DTRAC. In this tutorial we have chosen STRAC=ALL as the most useful report for application tuning. It shows the following for each thread traced:

- Basic **DB2** accounting record data
- **Environmental Indicators** section
- Elapsed Time Analysis section
- **SQL Statement Execution Counts** section
- **Buffer Pool Usage Analysis** section, including Global Buffer Pools
- Lock Activity section, including Global Locks
- I/O Parallelism section
- **Routines** section (stored procedures and user-defined functions)
- **DDF Summary** section (if distributed work was done)
- **Package/DBRM Overview** section (if accounting trace 7 is active)

These sections are included for detail traces that captured the relevant events:

- **SQL Summary** section with summary statistics per SQL statement (SQL events)
- **Database Summary** section with scans per page set (SCAN events)
- Database Lock and I/O section with locks and I/O data per page set (I/O or lock events)
- **Sort Summary** section (if any sorts were performed) (any detail trace)

6. Press **Enter** to validate your specifications.

These options are saved in your profile and used to initialize the fields the next time this panel is requested.

Be careful! Select only the data you want to print. This report is per thread execution (like an accounting trace report from DB2PM) and can generate a large amount of output.

7. Press **PF3** to review the generated JCL in edit mode.

The options you specified are inserted into a pattern job DZJPTRAC in BBPROF. You may want to copy this JCL into your own UBBPROF profile data set and modify it.

8. Review the remaining options.

There are many more print options than can be shown on the panel, such as lines per page or maximum pages to print. The sample job contains a short description of these options. Scroll to the bottom to review them.

9. Submit the job.

COMMAND ===> SUB

Of course, if you prefer, you can SAVE the JCL for later execution, or even CANCEL it completely.

- 10. When the job is completed, review the output.
- 11. Press **PF3** to return to the Batch Trace Print panel. You can issue another request now if desired.

Other Accounting Report Examples

Here are a few examples of workload-oriented reports based on the DB2 accounting record. For quick reports submitted online through the trace print panel, you will generally select one of the trace logs created by the Thread History (THRDHIST) trace for the time period you are interested in. However, these same accounting reports can be produced from any other summary or detail trace log. See "Print Offline Reports" on page 143 for more complete batch reporting options.

For a summary of total DB2 activity for the selected time period, you can first select an overview summary by time (broken into 30 minute intervals in this example), followed by a summary of all accounting data with useful averages, totals, and maximums for the complete period.

```
TSUM ==>T
TSTAT ==> SUMMARY
                        INTERVAL==>30M
```

To change the summary to a graphic format, edit the generated selection statements in the JCL before submitting the job:

```
TSUM=T, I = 30M, GRAPH = T0T (or AVG)
```

For a summary by plan (or other identifier), specify

```
TSUM=P
           (or A for authorization ID, and so on)
```

All the other summarization options of AUTHID, connect, buffer pool, location, and time are also available.

For a quick list of each thread, specify

```
LTRAC ==> Y
```

To generate a report of activity in each individual buffer pool per thread, specify

```
STRAC==>BPOOL
```

For a summary of this information per individual buffer pool for all selected threads, look at this same section in the TSTAT SUMMARY report mentioned above.

Other Detail Trace Report Examples

You may want to try other report combinations too. Here are a few examples from detail traces:

For an SQL statement summary per thread, sorted by Average CPU usage, followed by average SQL row processing statistics per statement:

```
LTRAC ==> Y
STRAC ==> SQL, SORTSQL=AC, SQLPOPUP
```

For a detail event trace per thread, with pop-up displays per SQL statement:

```
LTRAC ==>
DTRAC ==>
          Y
POPUP ==> SQL
```

For SQL statement text and EXPLAIN data for all dynamic SQL executed or BINDs of static SQL:

```
POPUP ==> (BIND-TEXT, EXPLAIN)
```

For a summary of I/O counts and wait times per database, table space, and plan (from an I/O trace):

```
DBIO ==> XP
```

To summarize by plan, database, and table space:

```
DBIO ==> PX
```

There are also many formatting options you can adjust:

NEWPAGE Control page breaks

WIDTH Specify wide (133) or narrow (81) output

LINECNT Adjust the number of lines printed per page

HEADING Suppress headings

MAXPAGES Limit the amount of output to prevent an unexpectedly high print volume

Online Views

You can export any windows-mode view to a data set or print it to a SYSOUT class using the **EXPort** command. The exported view can be used to supplement performance reports or can be downloaded to a workstation for use with a spreadsheet application.

When you enter the **EXPort** command, a panel is displayed requesting an existing data set name (or SYSOUT class) and formatting options, as shown in Figure 117.

Export a View for Printing

```
----- Export Open Data Set -----
COMMAND ===>
LIBRARY (PDS):
  Proj ect
  Group
                ===>
  Type
                ===>
  Member
                              Replace (Y/N)? YES
                ===>
Other partitioned or sequential data set:
  Data Set Name ===>
  Volume serial ===>
                            If not cataloged
Export Options:
                ===> REPLACE Replace or Append if sequential data set
  Di sposi ti on
  Output format ===> ASIS ASIS or CSV
  Li nes/Page
                ===> 0
                            ASIS format only (NNN)
  Sysout Class
                            If specified, overrides other data set options
               ===>
Press END to save changes and export report.
Type CANCEL to return to previous panel without saving changes.
```

Figure 117. View Export Panel

The output of the **EXPort** command includes all the rows of data associated with the view, even data that requires scrolling to be seen online. However, if the logical record length (LRECL) of the data set is less than the width of the view, the view data is truncated on the right.

Print Offline Reports

You can print

- Offline traces from a trace log data set or SMF records
- Offline Performance Reporter reports from both SMF data and DB2 tables

Batch Trace Print

Most scheduled batch reporting is done with the Performance Reporter reports either directly from SMF data or from that same data loaded (often summarized) in DB2 tables. However, this data is often not available to answer questions about the DB2 workload until the next day. The batch trace print facility is designed to fill the need for quick reports. All the trace summary accounting report formats are available, in any combination.

There are different types of input:

- One or more trace log data sets For example, the Thread History trace.
- The archived trace logs (without reloading to VSAM) For example, thread history from two weeks ago.
- An SMF history file containing DB2 Accounting records or I/O trace IFCIDs
- The live SMF data sets
- A GTF trace data set

A batch utility job, DZTBTRAC, is provided in your BBSAMP data set to print these reports. There is also a sample JCL member DZTBPRNT you can use when you want to generate multiple reports or print accounting reports from SMF data. The control statements for several sample reports are provided in BBSAMP member DZJPnnnn, with comments to point out some of the most useful variations.

The trace data shown in the batch reports is in the same format and content as the online displays. This includes LTRAC, STRAC, DTRAC, DTRAC pop-ups, TSTAT, and the TSUMx and DBIOx series of displays. Many of these displays can also be combined into one report. For example, a report can consist of both LTRAC and DTRAC data. Selection options, such as plan, authorization ID, or date can be used to narrow the scope of a report. In addition, you can focus in on just one area of interest, such as buffer pool activity by individual pool.

All of the report options described in "Print Online Reports" on page 136 are also available by directly editing and submitting the batch trace print job, first specifying the input file and the reports to be printed.

Trace Print from a TLDS

To print a trace log data set, use the JCL provided in BBSAMP members DZTBTRAC, as shown in Figure 118. Specify the DSN of the log with the TLDS parameter. Multiple TLDSs can be concatenated.

Specify JCL Statements

```
//
            JOB (ACCT), 'NAME'
//DZTBPRNT PROC TLDS=NULLFILE,
                                             INPUT TRACE DATA SET
                TDI R=NULLFI LE,
//
                                             INPUT TRACE DIRECTORY
//
                SMF=NULLFILE,
                                             INPUT UNLOADED SMF FILE
//
                GTF=NULLFI LE.
                                             INPUT GTF FILE
//
               ARC=NULLFI LE.
                                             INPUT ARCHIVED TRACE DATA SET
//
               PFX=' HI LVL. RUN. LI B'
                                             DSN PREFIX OF BBLINK
//PRINT
          EXEC PGM=DZTBPRNT, REGION=4M, PARM='GMWK=128K'
//*
                                            INCREASE GMWK FOR LARGE TRACES
//STEPLI B
             DD DI SP=SHR, DSN=&PFX. . BBLI NK
//SYSPRI NT
            DD SYSOUT=*
                                             INPUT LIST AND DIAGNOSTICS
//SYSUDUMP
            DD SYSOUT=*
                                             ABEND DUMPS
//STD1
             DD SYSOUT=*
                                             DEFAULT REPORT OUTPUT
//*
//*
                ONLY ONE OF THE FOLLOWING INPUT DD'S MAY BE SPECIFIED
       ===>
//*
                IF NONE IS SPECIFIED, DEFAULT INPUT IS LIVE SMF DATASET
       ===>
//*
//TRACI NO1
            DD DI SP=SHR, DSN=&TLDS
                                             TLDS INPUT
            DD DI SP=SHR, DSN=&TDI R
                                             TLDS INPUT THRU TRACE DIR
//TRACEDI R
            DD DI SP=SHR, DSN=&SMF
                                             SMF INPUT
//SMFIN
                                             GTF INPUT
//GTFIN
            DD DI SP=SHR, DSN=&GTF
//ARCI N
                                             ARCHI VED TLDS I NPUT
            DD DI SP=SHR, DSN=&ARC
          PEND
//
//*
//*
                          ** SPECIFY INPUT FILE **
//PRINT
          EXEC DZTBPRNT, TLDS=' SYS5. DB2P. THRDHI ST. JUL01. T0001. V01'
            DD SYSOUT=*
//REPTDD1
                                            USER-DEFINED OUTPUT DD
            DD SYSOUT=*
//RPTSUM
                                            SAMPLE REPORT OUTPUT DD
//RPTWKLD
            DD SYSOUT=*
                                            SAMPLE REPORT OUTPUT DD
            DD SYSOUT=*
//RPTACCL
                                            SAMPLE REPORT OUTPUT DD
            DD SYSOUT=*
//RPTACCS
                                            SAMPLE REPORT OUTPUT DD
            DD SYSOUT=*
//RPTSQL
                                            SAMPLE REPORT OUTPUT DD
            DD SYSOUT=*
                                            SAMPLE REPORT OUTPUT DD
//RPTEVNT
            DD SYSOUT=*
                                            SAMPLE REPORT OUTPUT DD
//RPTEXPL
            DD SYSOUT=*
                                            SAMPLE REPORT OUTPUT DD
//RPTFAI L
                                            SAMPLE REPORT OUTPUT DD
//RPTDBI 0
            DD SYSOUT=*
            DD *
//*SYSIN
                                            FOR IN-STREAM REPORT STMTS
//SYSIN
             DD DSN=&PFX. BBSAMP(DZJPSUM)
                                             DEFAULT SUMMARY RPT
                                                                   (SUM)
//
             DD DSN=&PFX. BBSAMP(DZJPWKLD)
                                             WORKLOAD SUMMARY-TIME(SUM)
//*
            DD DSN=&PFX. BBSAMP(DZJPACCL)
                                             ACCTG DETAIL-LONG
                                                                    (SUM)
//*
            DD DSN=&PFX. BBSAMP(DZJPACCS)
                                             ACCTG DETAIL-SHORT
                                                                   (SUM)
//*
            DD DSN=&PFX. BBSAMP(DZJPSQL)
                                             SQL STATEMENT SUMMARY(D-SQL)
//*
            DD DSN=&PFX. BBSAMP(DZJPEVNT)
                                             THREAD DETAIL EVENTS (D-ANY)
//*
            DD DSN=&PFX. BBSAMP(DZJPEXPL)
                                             SQL TEXT/EXPLAIN
                                                                    (D-SQL)
//*
            DD DSN=&PFX. BBSAMP(DZJPFAIL)
                                             LOCK/EDM FAILURES
                                                                    (D-BASE)
//*
            DD DSN=&PFX. BBSAMP(DZJPDBIO)
                                             I/O SUMMARY BY DB/TS (D-I/O)
//*
```

Figure 118. JCL to Print a Trace (DZTBTRAC)

For detailed information about all the control statements in DZTBTRAC, see "Printing a Trace" in Volume 3 of the MAINVIEW for DB2 User Guide.

An example of the Accounting Summary Report produced when you submit this JCL is shown in Figure 119. It shows accounting totals, followed by a trace summary by plan.

BMC SOFTWARE REPORT: SUM	ACCOUN	TING SUMM	ARY REPORT			: 2 : 17MAR01 : 12: 16: 56
SU						
FIRST END 01MAR 14. 37 LAST END 01MAR 14. 38	. 35. 21		TOTAL	AVERAGE	MAXI MUM	MI NI MUM
NUMBER TRANS	4 E	LAPSED 0 LP-DB2 0	0: 10: 20 0 0: 08: 42 0	00: 02: 35 00: 02: 10	00: 09: 12 00: 07: 35	9,695 ms 9,694 ms
NORMAL TERM		PU PU- DB2	21 s 5 13 s 3	5,302 ms	20 s 12 s	183 ms
DEALLOC	3 W	AITS 0	0: 06: 53 0	0: 01: 43	00: 06: 11	
APPL END	0 S	QL	4, 958	1, 239	4, 954	4
DRAT INACT	0 G	YNC RDS	110	27	4, 954 27, 203 57	56 0
I FI READ	0 P	FCH PGS	26, 916	6, 729	26, 916	0
I FI READABNORMAL TERMIN DOUBT TERM	1 U	PD/COMT FR HIT RA	0 TI 0S:	0 VP= 2% F	0 IP=100%	0
KEY INDICA	TORS					
TOTAL DDL = 4	TCU 4 052					
SQL: SELECT= 0, FE SQL: DYNAMI C (PREPARE) =						
I/O RSP: SYNC= 62 m	is, ASYNC=	133 ms				
LOCK SUSPENSIONS =	z					
ELAPSE					7)	
	ENTS AVG/EV				5 50 75	100%
ELAPSED TIME		~	50.0		*****	
IN DB2 IN APPLICATION		7, 554 5, 246	ms 59.0 ms 40.9	, i		
T0TALS			s 100.0		*******	****
WAITS IN DB2 (LOCAL)	7 100	mc 703	ms 5.4	n *		
LOCK/LATCH I/O WAIT	7 100 320 12	ms 3, 927	ms 30.6		*	
LOG WRITE I/O	5 4, 083	us 20	ms 0.1	5 <		į
OTHER READ I/O OTHER WRITE I/O	4 40 0 0	ms 159 us 0		24 <		
UNIT SWITCH EVENTS				İ		İ
COMMIT/ROLLBK OPEN/CLOSE	4 16 8 159 16 13 2 27	ms 63	ms 0.4	9 < 1 *		
SYSLGRNG	16 13	ms 208	ms 1.6	52 <		
DATASPACE MGR	2 27	ms 53	ms 0.4	1 <		
OTHER ARCH. LOG(QIS)	7 7, 638 0 0	us 53 us 0	us 0.4	1 <		
ARCH. READ(TAPE)	0 0 0 0 0 0	us 0	us 0.0	00		ļ
DRAIN LOCK CLAIM RELEASE	0 0	us 0	us 0.0 us 0.0			
PAGELATCH CONT.	0 0	us 0	us 0.0			
SPAS SERVER TCB Force-at-commit	0 0 0 0 0 0 0 0	us 0	us 0.0 us 0.0			
WAITS IN DB2 (GLOBAL)			us 0.0			
LOCKS	15 2, 903 0 0	us 44				
	0 0 383 17		us 0.0 ms 50.6		****	-
*NOT ACCOUNTED			us 0.0			į
ACTI VI TY	BUFFE		TI VI TY BP2			 BP10
GETPAGESSYNC READS	2, 545 320	14 11	592 0	1 0	6 0	38 0
GETPAGES/READI O	8. 0	1.3	0. 0	0. 0	0. 0	0. 0
COND. GP FAI LURES	0	0	0	0	0	0
SEQ. PREFETCH REQS.	22	2	0	0	0	6
LIST PREFETCH REQS.	1	0	0	0	0	0
DYNAMI C PREFETCHES. ASYNC PAGES READ	16 284	1 47	0	0 0	0	0
PAGES/PREFETCH REQ.	7. 3	15. 7	0. 0	0. 0	0. 0	0. 0
BMC SOFTWARE REPORT: SUM	ACCOUN	TING SUMM	ARY REPORT	•		: 4 : 17MARO1 : 12: 16: 56
		STEM TRAC				
PLAN COUNT ELAPS	ED CPU	#STMTS G		APSED C	CPU #STMT	
DSNTI A41 11 483	ms 172 ms	11. 3	162. 3 5, 30	9 ms 1,88	89 ms 12	4 1, 785
DSNTI A41 11 483 DSNTI B41 1 18 DSN8CCO 2 00: 01: RXDB2 1 6, 086	s 5,954 ms 07 19 ms	1. 0 12. 0	ZU. U 1 7. 0 00: 0	. os 5,95)2:13 3	94 ms 88 ms 2	1 20 4 14
RXDB2 1 6, 086	ms 2,633 ms	245. 0	1, 160 6, 08	66 ms 2, 63	33 ms 24	5 1, 160
********	***** END O	F SUMMARY	ENTRIES *	*******	*******	*****

Figure 119. Accounting Summary Report

All control of the input and formatting is done through a series of keywords in the input job stream (or in a PDS member) under ddname SYSIN. Keywords that apply to all requested reports can be specified following a label of GLOBAL. Keywords that apply to a specific report must be specified following the REPORT label. An example of two report requests is shown in Figure 120.

Specify Request Keywords

```
GLOBAL TI ME=1300-1500
        BIND-TEXT and EXPLAIN FROM TSO
REPORT
        REPORTI D=DAI LY1, LTRAC=YES, NEWPAGE=TRAN,
        POPUP=(BI ND-TEXT, EXPLAI N, OPEN),
        CONNECT=TSO,
        TITLE1='DETAILS OF BIND AND EXPLAIN',
        TITLE2='WITH STATS FROM OPEN',
                                       COMMENTS ABOUT THE REPORT
        DDN=OUTPUT1, WI DTH=WI DE
        FULL EXAMINATION OF CERTAIN SPECIAL TRANSACTIONS
        REPORTI D=SPECI ALS, LTRAC=YES, STRAC=SUMMARY, DTRAC=YES, POPUP=ALL,
REPORT
        NEWPAGE=(TRAN, FI RSTEVENT), LEVEL=3,
        PLAN=(PAY+++++, ACCT1+++), CONNECT=I MSP,
        AUTHI D=(USR1, USR5)
```

Figure 120. Sample Report Requests

The GLOBAL keyword TIME limits the trace output to 1pm to 3pm for both reports.

The first report prints the one-line LTRAC entry on a new page for each transaction of the selected TSO threads and the pop-ups for BIND-TEXT, EXPLAIN, and OPEN after that one-line entry for each transaction. The report is written on ddname OUTPUT1.

The second report prints the one-line LTRAC entry, the STRAC accounting summary, and all DTRAC events and pop-ups for selected plans from two specific IMS users. The report is written on ddname SPECIALS.

For detailed information about each of the request keywords you can use, see "Printing a Trace" in Volume 3 of the MAINVIEW for DB2 User Guide.

Trace Print from SMF Records

This same batch utility (DZTBTRAC), shown in Figure 118 on page 144, can be used to print summary trace reports from DB2 accounting records written to GTF or SMF, either from an SMF history tape or from the live SMF data sets.

In addition, the following I/O analysis reports can be produced from an SMF or GTF file that includes the I/O trace records (IFCIDs 06-10):

DBIO=X

I/O analysis by database and table space

This report can be summarized by many different summary key combinations, such as plan, database, table space or database, table space, plan. See "Special Report Summarization Options for DBIO" in Volume 3 of the MAINVIEW for DB2 User Guide for examples.

DBIO=A

I/O analysis by AUTHID

DBIO=C

I/O analysis by connection name

DBIO=F

I/O analysis by buffer pool

DBIO=L

I/O analysis by location

DBIO=P

I/O analysis by plan

DBIO=T

I/O analysis by time interval

Other detail trace events are not extracted from SMF or GTF. In addition, you cannot process SMF or GTF files in the same run with TLDSs.

Performance Reporter Reports

Performance Reporter is an offline analysis system that produces reports that can be used to evaluate DB2 system and application performance. These evaluations can be used for DB2 planning, forecasting, and performance management.

Several reports can be produced from SMF extract files without loading the data into DB2 tables. This includes accounting short and long reports and statistics short and long reports.

However, the performance data tables are the main source of historical information for Performance Reporter. You can print any number of reports produced from the summary and detailed accounting tables, or statistics, buffer statistics per pool, and audit tables.

Reports from SMF

Selective or total accounting reports, in either a short or a long format, can be printed from DB2 accounting records extracted from one or more SMF files. For example, you can select from a specific time period or by plan, authorization ID, and so on. The reports also can be summarized by various criteria.

Use the DPREPORT batch job to print accounting or statistics reports, in either a short or a long format. Figure 121 on page 149 shows sample job control statements for producing an accounting long report ordered by primary authorization ID and plan name, summarized in 8-hour intervals.

Specify Job Control **Statements**

```
//DPRACCT JOB
//*_______
            JOB TO PRODUCE AN ACCOUNTING LONG REPORT
//*
            ORDERED BY PRIMARY AUTHID AND PLAN NAME
//*
            FROM 00: 00: 00 - 23: 59: 59 HOURS FOR OCT. 16 - 18,
            SUMMARIZED IN INTERVALS OF 8 HOURS (480 MINUTES).
//*
            ONLY AUTHIDS OF BPL2X OR THOSE BEGINNING WITH CJN*
//*
            ARE SELECTED FOR THIS REPORT.
//*-----
           EXEC PGM=DPREPORT, REGION=4096K
//STEP1
//STEPLI B
          DD
                DSN=HI LVL. DPRLOAD, DI SP=SHR
//DPDACCT DD
                DSN=HI LVL. ACCT31, DI SP=SHR
//SYSPRINT DD
                SYSOUT=*
//DPDPRINT DD
                SYSOUT=*
//SYSOUT
           DD
                SYSOUT=*
//SYSUDUMP DD
                SYSOUT=*
//SORTWK01 DD
                UNI T=SYSDA, SPACE=(TRK, (45, 15)), DI SP=(, DELETE, DELETE)
                UNIT=SYSDA, SPACE=(TRK, (45, 15)), DISP=(, DELETE, DELETE)
//SORTWK02 DD
//SORTWK03 DD
                UNI T=SYSDA, SPACE=(TRK, (45, 15)), DI SP=(, DELETE, DELETE)
                UNI T=SYSDA, SPACE=(TRK, (45, 15)), DI SP=(, DELETE, DELETE)
//SORTWK04 DD
                UNIT=SYSDA, SPACE=(TRK, (45, 15)), DISP=(, DELETE, DELETE)
//SORTWK05 DD
                UNIT=SYSDA, SPACE=(TRK, (45, 15)), DISP=(, DELETE, DELETE)
//SORTWK06 DD
//SORTWK07 DD
                UNIT=SYSDA, SPACE=(TRK, (45, 15)), DISP=(, DELETE, DELETE)
//SORTWKO8 DD
                UNI T=SYSDA, SPACE=(TRK, (45, 15)), DI SP=(, DELETE, DELETE)
           DD
//SYSIN
REPORT=ACCT
REPTYP=LONG
RSMFI D=SYSB
RDB2I D=DB2F
FRDATE=20010516
FRTI ME=000000
TODATE=20010518
TOTI ME=240000
INTVAL=480
RORDER=(PRAUTH, PLANAM)
FI LTYP=(PRAUTH)
FI LTR1=(BPL2X, CJN*)
//
```

Figure 121. Sample DPREPORT Job Control Statements for Accounting Reports

See "SMF Reporting Facilities (DPREPORT)" in the MAINVIEW for DB2 Performance Reporter User Guide for detailed information about each of the JCL control statements in the DPREPORT job.

Reports from DB2 Tables

Printing workload reports is usually done from the DB2 tables of performance data supported by Performance Reporter. This gives you long-term history and trending, as well as the full flexibility of SQL for defining your own reports in addition to the predefined set. See "DB2 Tables Reporting Facilities" in the MAINVIEW for DB2 Performance Reporter User Guide for more information.

Performance Reporter provides predefined reports using SQL statements, which can be run through a batch reporting facility (DPRREPT) or through QMF queries. DB2 performance charts and plots are also provided, which are available through QMF only. Other queries and reports based on the performance data tables can also be defined.

Predefined Reports

The prepared reports included with Performance Reporter show DB2 system workload to help the DB2 performance analyst, capacity planner, or service manager solve specific DB2 problems. These reports are generated from accounting, statistics, and audit data.

With these reports, standard reporting can be run on a daily or weekly basis or both.

Daily run

The queries processed by the batch reporting program, DPRREPT, from the detail statistics (queries STxxx) and detail accounting (queries ACxxxx) tables are set up to produce a set of daily reports on the data loaded from the previous day (current date minus one). The sample JCL in BBSAMP named DPRRPT includes all distributed reports. Run these reports once, select those ACxxxx and STxxx reports you want to review daily, and create a job for this daily run.

Note:

If you do not load detail accounting records into table DMRACDTL, but only data summarized by hour or day into table DMRACSUM, delete the ACxxxx reports from the job and modify the date selection on the SAxxxx reports to produce your daily reports. The report results will be the same. Only the detailed exceptions report cannot be produced.

Weekly run

The queries processed by the batch reporting program, DPRREPT, from the summary accounting table (queries SAxxxx) are set up to produce a set of weekly reports on the data from the previous week (current date to current date minus seven). Select the SAxxx reports you want to review weekly and create a job for this weekly run.

Any of the distributed SQL queries can be modified or used as a model to produce queries to satisfy ad hoc reporting needs. However, the flexibility of QMF, in general, makes it the better vehicle for such reporting. An added advantage with QMF is that the procs provide an easy way to select a specific time period for reporting without modifying the queries themselves.

QMF Queries

QMF can be used to run distributed reports or tailor custom performance reports and charts. A generalized QMF procedure, DZPRQRPT, runs predefined Performance Reporter queries and formats the reports using the distributed Performance Reporter forms. The predefined reports produced with QMF are the same as those produced with the batch reporting facility, DPRREPT. However, with QMF, you can select a range of dates for these reports.

You must enter the QMF program to use this procedure. Detailed instructions to run and use QMF can be found in the IBM Query Management Facility Learner's Guide.

To run the predefined Performance Reporter queries from QMF, type the command:

RUN DMRPR. DZPRQRPT (&REPORT=report name

where report name is the name of the report you want to produce. For example, to run the DB2 Accounting Overview Report, type

RUN DMRPR. DZPRQRPT (&REPORT=ACOVERA

The report table date range prompts FROM and TO might appear when running these queries under QMF. Type the date range you want using the standard TSI format:

' YYYY- MM- DD- HH. MM. SS. TTTTTT'

Or, you can set global report variables by typing one of these procs:

RUN DMRPR. DZPRQDAT

RUN DMRPR. DZPRQDEF

Once you have set these global variables, they will be used by all Performance Reporter report queries for the duration of the QMF session.

To produce QMF batch reports, use the sample jobs in BBSAMP member DZPRQBAT.

Customizing Your Own Reports

Once you have used the Performance Reporter facilities to load data into DB2 tables, you may want to use your own reporting tools to create customized reports.

However, since Performance Reporter uses either QMF or a generalized report generator to provide reporting and charting facilities, the entire report is defined by the SQL select statement used to read the data tables. Thus, it is very easy to create customized reports for a specific requirement. The SQL select statements used to produce the distributed reports and charts are available, within the QMF or DPRREPT environments, as models in tailoring new reports or charts.

The JXREPT program is designed to run any SQL SELECT statement against the Performance Reporter tables and report the results.

See "Customizing Reports" in the MAINVIEW for DB2 Performance Reporter User Guide for more information.

One example of a custom report you may want to create is to change the time interval for reporting statistics data.

The default statistics reports show statistics by the DATETIME stamp in each record. To provide a historical view, you may want to modify the distributed reports to show statistics grouped by a longer time interval. To simplify this type of reporting, the statistics tables include columns for several other date and time values, such as DATE, MONTH, DAY, TIME, and HOUR.

Data is not *spread* across intervals. Note:

An example of a report by DATE and HOUR is in BBPARM member STOVERH, as shown in Figure 122. See "Reporting Statistics Data by Time Interval" in the MAINVIEW for DB2 Performance Reporter User Guide.

	I - 03- 01 00: - 03- 19 23:			DB2 ST	ATI STI C	S OVERVII	EW REPO	RT - AVER	AGES		REPORT DA	LO	- 03- 25	- SANJOSE
	CREATE PH	IASE 2	SYNC		SQL	SQL	SQL	GETPAGES	PAGE	READ	WRITE	EDM LOC	WRT	LOCK
DATE / HOUR	THREADS C			ABORTS	MANI P.	CONTROL			UPDATES	I/0	I/0	LOADS	CALLS	SUSPEND
2001-03-01 00	1	0.0	0.0	0.0	0.0	0. 0	0.0	6.0	0. 0	1.0	0.0	0.0	0.0	0.0
2001-03-01 01	0	0.0	0.0	0.0	0.0	0. 0	0.0	0.0	0. 0	0.0	0. 0	0.0	0.0	0.0
2001-03-01 02	8	0.6	0. 5	0. 1	1. 2	2. 2	0.0	367. 7	176. 7	15. 7	1. 3	1.3	4.0	0.0
2001-03-01 03	3	0.3	1.0	0.0	0.6	0. 0	0.0	64.6	30. 6	1.6	4. 0	0.0	2.0	0.0
2001-03-01 04	1	0.0	1.0	0.0	253. 0	0. 0	0.0	520. 0	0. 0	15.0	0. 0	2. 0	0.0	0.0
2001-03-01 05	1	2.0	0.0	0.0	1.0	0. 0	0.0	10.0	0. 0	8. 0	0. 0	0.0	0.0	0.0
2001-03-01 06	14	1.0	0. 0	0.0	1.0	0.8	0. 0	17.3	0. 0	4.8	0. 0	0. 2	0.0	0.0
2001-03-01 07	10	0. 6	0. 7	0.0	1.4	1. 5	0. 0	304. 6	168. 1	4. 7	2. 4	0.0	3. 4	0.0

Figure 122. Statistics Overview Report by DATE and HOUR

Index

Symbols	application trace
# prefix	tutorial example
definition 27	access services 70
#SQLM monitor	accessing EXPLAIN 124
tutorial example 27	activating 66
* (asterisk)	additional options 62
wild card	analyzing DB2 workload 93
tutorial example 98	avoiding expensive lock event traces 81
+ (plus)	BIND-TEXT pop-up 118
qualifier	buffer pool activity 74
tutorial example 98	collecting I/O events 103
@ prefix	database summary 79
definition 27	defaults 61
	detail entry display (DTRAC) 83, 118, 127
_	detail event summaries 76
A	detail events 64, 103
accessing	elapsed time 73
MAINVIEW 6	error messages 66
accounting records	exception filters 63
tutorial example	EXPLAIN pop-up 119
LTRAC display 71	I/O analysis 86, 102
STRAC display 72, 97	improve performance 67, 112
TSTAT display 85	list of current 60, 69
active requests	list of historical data sets 69, 88, 101, 136
list of monitors 26, 32	list of trace entries (LTRAC) 71
active threads	lock and I/O events 80
all 11	LOCK-SUMMARY pop-up 119
multiple DB2s 13	logging 65
Active Timer Request list	long-running threads 69
tutorial example 26, 32	managing log data sets 88, 136
select by area 33	narrowing 63
Activity Overview view 8, 15	navigating 70, 82
Activity Rates view 9	package/DBRM overview 75
Add SSI Context Definition panel 43	printing 88, 106, 136
All Active Threads view 11	qualifying 62
analyzer	sort summary 81
tutorial example	SQL statement pop-up 78, 84, 126
Primary Option Menu selection 7	SQL statement summary 76, 82, 125
application I/O analysis	starting 60, 103, 113
tutorial example	summary by authorization ID 99
activity by package/program 86	summary by connection name 99
activity by package/program 60 activity by page set 86, 104	summary by DDF location 99
activity by plage set 86, 104	summary by plan 96
activity by SQL statement 87	summary by relative day 99
asynchronous I/Os 86, 104	summary by time 94, 100
collecting I/O events 103	summary entry display (STRAC) 72, 97
detail I/O events 87, 103	summary of all threads (TSTAT) 85, 98
printing I/O reports 106	test applications 67, 112
running a system I/O trace 103	tuning 59, 69
	application transfer
summarized trace events 86, 87, 104 synchronous I/Os 86, 104	tutorial examples 28, 30, 101
	CT command 113
system-wide traces 102	LOG command 38, 99
total measurements 104	SM command 26
	ST command 60, 113
	to full-screen mode 16

application tuning with trace	Buffer Pool Page Set GBP-DEP Summary view 48 Buffer Pool Page Set Summary - Session view 25
tutorial example 59, 69 AREA command	Buffer Pool Rates Detail view 18 Buffer Pool Statistics - SSI view 17
tutorial example 27, 33	Build 1 ool buildies BBI (16W 1)
asterisk (*)	
qualifier	C
tutorial example 98	cache
ASYNC parameter	statistics
tutorial example 86	tutorial example 24
ATTN key	cancel thread
terminating GO	from DUSER display 12
tutorial example 34	card
audit trail 38 authorization	quick reference 1
for tutorial exercises	CATALOG hyperlink 128, 129
cancel a thread 12	check status and activity 7, 15 codes
issue DB2 commands 40	severity 31
issue RESET USERID command 59	commands
modify or purge a monitor 29	application transfer
start an application trace 59, 60, 102	tutorial examples 26, 28, 30
update BBPARM data set 59	windows to full-screen mode 16
automatic multiple requests startup 26, 32	DB2
automatic refresh mode	displaying response 40
monitor history display	issuing from MAINVIEW for DB2 40
tutorial example 34	COMMIT
automatic warning 26, 28, 32	execute SQL 114, 126
AutoOPERATOR	compare threads 82
triggering EXECs 28	CONACT view
average data measurement 27	tutorial example 42
	CONASEL view
В	tutorial example 42
	console
balancing	MVS
table space allocations	warning messages sent to 28
tutorial example 25	contention
batch trace print tutorial example 88, 106, 136, 143	lock tutorial example 19, 32
data entry panel 89, 107, 137	with data sharing 50
SQL prototype 120	context
BFRPL view	defining
tutorial example 17	for a data sharing group 42
BFRPLD view	selecting 42
tutorial example 17	CONTEXT command
BFRPLHD view	tutorial example 14, 42
tutorial example 18	count data measurement 27
bind	critical problems
text pop-up	review
tutorial example 84, 118	tutorial example 30
BLKDMRW	CT application transfer
default set of monitors 26	tutorial example 113
blocking requests	current
automatic start 26	hit ratios 18
buffer pool	SQL statement
tutorial example	full text 12, 122
activity summary (STRAC) 74	SQLID 115, 122, 126
all defined pools 17	thread activity 11
hit ratios 18	multiple DB2s 13
one pool 17	Current Traces application
tune for data sharing group 54	tutorial example 60, 69

D	DBRM
Data Collection Monitor list application	overview (STRAC)
tutorial example	tutorial example 75
scroll 27	defaults
select by area 27, 33	for starting a monitor 27
sort 27	for starting a trace 61
data selection identifiers	query number 116
tutorial example 138	starter set of monitors 26
data sets	definitions
tutorial examples	all SSI contexts 42
I/O analysis 128	detail trace
data sharing	tutorial example
buffer pool tuning 54	avoiding expensive lock event traces 81
current group activity 45	BIND-TEXT pop-up 118
defining the group context 42	database summary 79
lock contention 50	detail entry display (DTRAC) 83, 127
monitoring a group 41	display level 83
page set considerations 46	event summaries (STRAC) 76
Data Sharing Wizard GBP Directory Detail view 56	EXPLAIN pop-up 119
Data Sharing Wizard GBP Directory Entries view 56	I/O analysis 87, 104, 105
Data Sharing Wizard GBP Options view 55	lock and I/O events 80
Data Sharing Wizard GBP Size Activity view 57	LOCK-SUMMARY pop-up 119
Data Sharing Wizard GBP-DEP/Member view 47	navigating 82
Data Sharing Wizard Group Members view 54	sort summary 81
DB2	SQL statement pop-up 78, 84, 126 SQL statement summary 76, 82, 125
accounting record	starting 64, 103
LTRAC display 71	testing SQL 118
STRAC display 72, 97	detail user display
commands	tutorial example 11, 122
displaying response 40	directory
issue from MAINVIEW for DB2 40	tutorial example
Exceptions display	too few entries 55
tutorial example 31	DMAREAZ view
messages	tutorial example 36
logging 38	DMRBEX00
selecting current target DB2 39	logging DB2 messages
viewing a subset 39	tutorial example 38
Performance Management	DMWARN view
isolating problems 5, 97	tutorial example 35
status 7, 15	DOBJ view
detail view 15	tutorial example 37
DB2AUTH keyword	DTRAC
tutorial example 62, 103	display
DB2CONN keyword	avoiding expensive lock event traces 81
tutorial example 28	BIND-TEXT pop-up 118
DB2EX display	EXPLAIN pop-up 119
tutorial example 31	LOCK-SUMMARY pop-up 119
DB2PLAN keyword	SQL statement pop-up 84
tutorial example 62	testing SQL 118
DB2TRACE authorization parameter	tutorial example 83, 127
for tutorial exercises 59	DUSER display
DBIO display	tutorial example 11, 122
tutorial example 86, 104	DZJPTRAC skeleton JCL member
DBIOD display	tutorial example
tutorial example 128	printing a trace 90, 108, 139
DBIOP display	DZTBPRNT program 107, 143
tutorial example 105	DZTBTRAC utility 143
DBIOS display	·
tutorial example 87	

E	expand (continued)
Easy Menus	tutorial examples (continued)
EZDB2 (one DB2)	to DBIOS display 87
tutorial example 14	to detail entry display (DTRAC) 83, 127
EZDSSI (multiple DB2s)	to DTRAC display 118
tutorial example 8, 35	to DUSER display 122
elapsed time analysis	to elapsed time analysis 73
tutorial example 73	to EXPLAIN PLAN_TABLE display 122, 123
Enhanced Journal Facility 39	to EXPLAIN pop-up 119
error messages	to lock and I/O events 80
	to LOCK-SUMMARY pop-up 119
current traces tutorial example 66	to package details 75
event pop-up displays	to sort summary 81
tutorial example	to SQL statement pop-up 78, 84, 126
-	to SQL statement summary 76, 82, 125
BIND-TEXT 84, 118	to SQL statement text 78, 126
EXPLAIN 84, 119	to STRAC display 71, 97
LOCK-SUMMARY 84, 119	to TSTAT display 85, 98
LOCK-TMO 84	to TSUMP display 96
MULTI-INDEX 84	EXPLAIN from edit 116
SQL statement 84, 119	EXPLAIN hyperlink
exception	from a trace
conditions	tutorial example 124
system 13	EXPLAIN PLAN_TABLE
user 13	output panel 117, 123
warning monitors 13	qualifier panel 116, 122
locate time	tutorial example
tutorial example 38	accessing from a trace 126
Exception Conditions view 13	accessing more details 132
Exception Filters	information for one plan 132
tutorial example 63	EXPLAIN pop-up
exception messages	tutorial example 84, 119
displaying 31	EXPort command 142
EXEC	
application transfer command	_
tutorial example 30	F
triggered when threshold is exceeded 28	Fast Menu 16
execute SQL	fetches
tutorial example 114	execute SQL
from a trace 126	tutorial example 114, 126
results of execution 115	filtering data
expand	tutorial examples 23
tutorial examples	filters
BIND-TEXT pop-up 118	tutorial example 63
from DBIOD display 128	FIND command
from DBIOR display 128, 129	tutorial example 38
from DTRAC display 118, 119	format
from DUSER display 122, 123	options
from LTRAC display 71, 85, 86	batch trace print 91, 141
from SQL statement pop-up 78, 126	outen trace print >1, 1.1
from TSTAT display 86	
from USERS display 122	
to a subset of threads (LTRAC) 96	
to buffer pool activity 74	
to current trace log data set 100	
to database summary 79	
to DB2 catalog information 128	
to DBIO display 86, 104, 105	
to DBIOD display 128	
to DBIOP display 105	

G	I
global	I/O analysis
lock contention 50	tutorial example
Global Lock Wizard view 50	activity by package/program 86
Global Lockout Events view 52	activity by page set 86, 104
GO command	activity by plan 86, 105
tutorial example 34	activity by SQL statement 87
goals	asynchronous I/Os 86, 104
response time	balance table space allocations 25
monitoring 37	cache statistics 24
graph	collecting I/O events 103
tutorial example	detail I/O events 87, 103
average values 94, 101	detail trace summary 80
CPU time 72	Primary Option Menu selection 103, 104
elapsed time 72, 73	printing I/O reports 106
I/O wait time 86, 87	running a system I/O trace 103
monitor history display 33, 36	summarized trace events 86, 87, 104
package/DBRM overview 75	synchronous I/Os 86, 104
Primary Option Menu selection 94, 100	system-wide traces 102
total values 95	total measurements 104
trace summary by time 94, 100	volume summary 23
warning status of active timer requests 26, 32	with data sharing 46
workload objectives 37	improving performance
group buffer pool	tutorial example 67, 112
dependent page sets 47	index administration
tuning 54	tutorial example
GROUPSQL keyword	access more details 134
tutorial example 64	information for one index 134
tutoriai example 04	INPUT mode
	monitor history display
H	
	tutorial example 34 interval
headers 141	
suppress 141	counts
help	tutorial example 9 default timer request 28
commands 23	
tutorial example 29, 48	INTERVAL keyword Trace Summary by Time display
history	tutorial example 95
expand button	
tutorial example 100	isolating performance problems 5, 97
reviewing recent	
tutorial example 15	J
short-term 26	T 11
trace directory	Journal log
tutorial example 69, 88, 101, 136	Enhanced 39
workload	finding exception messages 99
analyze recent 94	viewing a subset of messages
review past 100	from current target DB2 39
hit ratios 18	warning messages sent to 28
host variable support 115, 116, 126	
hyperlink	K
CATALOG	
tutorial example 128, 129	key indicators
EXPLAIN 122, 124	STRAC display
PT 123	tutorial example 72, 97
SQLTEXT(EXPLAIN) 78, 126	TSTAT display
to RxD2	tutorial example 85, 98
from a trace 124	
from DBIOD 128	
from DBIOR 129	
from DUSER 122, 123	
from SQL statement pop-up 78, 126	

to catalog data 128, 129

L	log
LEVEL keyword	application transfer
tutorial example 83	tutorial example 38, 99
LINECNT keyword 141	data sets
LKBWZ view	displaying current 100
tutorial example 21	displaying history traces 69, 101 logging a trace 65
LKBWZSSI view	printing a trace 88, 106, 136
tutorial example 53	display
LKCONZ view	selecting current target DB2 39
tutorial example 21	tutorial example 38
LKEVENT view	viewing subsets 39
tutorial example 19	keyword
LKEVSSI view	tutorial example 28
tutorial example 52 LKRESD view	logging
tutorial example 20, 53	DB2 messages
LKRESNRZ view	selecting current target DB2 39
tutorial example 20, 52	tutorial example 38
LKRESZ view	viewing a subset 39
tutorial example 20, 52	LOGTRAC keyword
Local Buffer Pool Statistics Detail view 17	tutorial example 62, 103
location	long-running threads
connecting to remote 122, 130	tracing 69
lock	LTRAC
analysis	display
avoiding expensive traces 81	scrolling 71
detail trace events 81	tutorial example 71
detail trace summary 80	
global contention 50	M
hot spots in tables 52	
resource information 20, 52	MAINVIEW
see plans 53	accessing tutorial example 6
timeouts and deadlocks 19, 50	Selection Menu
contention	tutorial example 6
global 50	maximum PLOT graph values
tutorial example 19, 32	tutorial example 33, 36
pop-up	maximum warning threshold value
summary 84, 119	starting a monitor 28
timeout 84 Lock Wizard Global Members view 51	MAXPAGES keyword 141
Lock Wizard Global/Local Contention view 51	messages
Lockout Blocker/Waiter Summary view 21	DB2 38
Lockout Connection Summary view 21	exception
Lockout Events view 19	displaying 31
Lockout Global Blocker Waiter Summary view 53	tutorial example 13
Lockout Resource Conflict Detail view 20, 53	MAINVIEW for DB2 38
Lockout Resource Number Summary view 20, 52	origin identifier 39
Lockout Resource Summary view 20, 52	viewing a subset
,	from current target DB2 39
	MESSAGES option
	tutorial example 31
	minimum warning threshold value
	starting a monitor 28
	MODIFY (M) line command
	tutorial example 29 modifying requests
	tutorial example 29
	tatoriai champic 2)

monitor	P
a data sharing group 41	package
area summary (DMAREAZ) 36	1 0
definition 26	overview (STRAC)
tutorial example	tutorial example 75
defaults 28	page set considerations
graph of warning status 26, 32	
history display 33, 36	with data sharing 46 views
isolating problems 26	
list of active timer requests 26, 32	status 22
looking at different workloads 27	Page Set Cache view 24 Page Set GBP-DEP Status view 49
modifying 29	Page Set GB1-DE1 Status view 49
multiple requests 26, 27	parameters
Primary Option Menu selection 7, 26	service request
replicating 29	tutorial example 28
resource 27	trace request
starting 26, 27, 28	tutorial example 62, 103
stopping 29	performance
threshold marker 26, 32	of a bad SQL statement
windows mode views 35	improving 67, 112
workload 27	of an existing application
warning summary (DWARN) 35	analyzing 67, 112
workload objectives (DOBJ) 37	problems
Monitor Summary by Area view 36	isolating 5, 97
Monitors in Warning view 35	Performance Reporter
multi-index pop-up	reports 148
tutorial example 84	PF10/22 (display next entry)
multiple	tutorial example 82, 119
DB2s	PF11/23 (display previous entry)
tutorial example 8	tutorial example 82, 119
requests	PF5/17 (Log Display REPEAT FIND)
automatic start 26, 32	tutorial example 38
MVS console	PF5/17 (Log Display transfer)
warning messages sent to 28	tutorial example 38, 99
	PF6/18 (GO)
N	tutorial example 34
IN	PF7/19 (scroll)
navigating between traces 70	tutorial example
between threads (STRAC display) 82	Data Collection Monitor list application 27
NEWPAGE keyword 141	DB2 Trace Entries display (LTRAC) 71
	Detail Trace Entry display (DTRAC) 83
0	Trace Summary by Time display (TSUMT) 94
O	PF8/20 (scroll)
objective	tutorial example
workload	Data Collection Monitor list application 27
monitoring 37	DB2 Trace Entries display (LTRAC) 71
Objectives Review view 37	Trace Summary by Time display (TSUMT) 94
overview	plan
of all DB2s	I/O analysis
tutorial example 8	across data sharing members 53
	PLAN administration
	tutorial example
	access more details 131
	information for one plan 130
	PLAN keyword
	tutorial example 96, 98
	±

PLOT	pop-up (continued)
use	SQL statement
automatic refresh mode 34	tutorial example 78, 84, 119, 126
exceptions only 34	usage 84
tutorial example 33, 36	Primary Option Menu
PLOTMAX keyword	tutorial example
tutorial example 28	access to analyzers, monitors, and traces 7
plus (+)	RxD2 112
qualifier	printing
tutorial example 98	reports 135
point and shoot	offline 143
tutorial examples	online 136
BIND-TEXT pop-up 118	screens
from DBIOD display 128	series of displays 30
from DBIOR display 128, 129	single display 30
from DTRAC display 118, 119	traces
from DUSER display 122, 123	SQL prototype 120
from LTRAC display 71, 85, 86	tutorial example 88, 89, 106, 136, 137
from SQL statement pop-up 78, 126	problems
from TSTAT display 86	analyze lock and I/O
from USERS display 122	tutorial example 80
to a subset of threads (LTRAC) 96	review critical
to buffer pool activity 74	tutorial example 30
to current trace log data set 100	product
to database summary 79	line transfer
to DB2 catalog information 128	to DB2 catalog information (RxD2) 128
to DBIO display 86, 104, 105	to other MAINVIEW products 34
to DBIOD display 80, 104, 103	to RxD2 112, 121
to DBIOD display 125	stacking 34
to DBIOS display 87	PROFILE command 39
to detail entry display (DTRAC) 83, 127	
	prototyping
to DTRAC display 118	SQL statements 112
to DUSER display 122	print results 120 PSBPGBPZ view
to elapsed time analysis 73	
to EXPLAIN PLAN_TABLE display 122, 123	tutorial example 48
to EXPLAIN pop-up 119	PSBPSZ view
to lock and I/O events 80	tutorial example 25
to LOCK-SUMMARY pop-up 119	PSCACHE view
to package details 75	tutorial example 24
to sort summary 81	PSGBP view
to SQL statement pop-up 78, 84, 126	tutorial example 49
to SQL statement summary 76, 82, 125	PSSTAT view
to SQL statement text 78, 126	tutorial example 22
to STRAC display 71, 97	PSVOLPS view
to TSTAT display 85, 98	tutorial example 47
to TSUMP display 96	PSVOLSSI view
pop-up	tutorial example 46
asterisk (*) indicator 84	PSVOLSZ view
BIND TEXT	tutorial example 23, 46
tutorial example 84, 118	
definition vii	Q
EXPLAIN	•
tutorial example 84, 119	QMF
LOCK-SUMMARY	queries 151
tutorial example 84, 119	qualifier
LOCK-TMO	wild cards
tutorial example 84	asterisk (*) 98
MULTI-INDEX	plus (+) 98
tutorial example 84	quick start
	reference card 1

ĸ	3
RANGES keyword	S line command
tutorial example 28	tutorial example
recent	select a workload monitor 27
thread history 94, 100	scans
reference card	by table space and index space 79
MAINVIEW for DB2 1	screen
refresh	printing
monitor history display	series of displays 30
tutorial example 34	single display 30
remote	scrolling
catalogs	tutorial example
accessing 130	Data Collection Monitor list application 27
locations	DB2 Trace Entries display (LTRAC) 71
connecting to 122, 130	Detail Trace Entry display (DTRAC) 83
REPLICATE (R) line command	Trace Summary by Time display (TSUMT) 94
tutorial example 29	selection criteria
report keywords	for workloads
tutorial example	starting a monitor 28
data selection 89, 108, 137	SEQ parameter
formatting options 91, 141	navigating between trace entries
SQL prototype 120	tutorial example 82
report samples	service
printing 135	objective
tutorial examples 91, 108, 109, 141	monitoring 37
report selection	service-level objective
batch trace print 89, 108, 137	workload
SQL prototype 120	monitoring 37
RESET USERID command	session
authorization	counts
for tutorial exercises 59	tutorial example 9
resource	severity codes
monitors 27	tutorial example 31
response time	single system image (SSI)
objectives	contexts
monitoring 37	defining 42
reviewing critical problems	selecting 42
tutorial example 30	using
reviewing history 15	tutorial example 8
RFIND command 38	SM application transfer
ROLLBACK	tutorial example 26
execute SQL 114, 126 RST keyword	SORT tutorial example
tutorial example 28, 62	by average I/O wait time 104
RUNNING mode	by maximum I/O wait time 104
monitor history display	by number of I/Os 105
tutorial example 34	by pages scanned 77
RX command 112, 121	by percent I/O wait time 86, 105
RX IX (indexname OBID)	by user ID 71
command 134	detail trace summary (STRAC) 81
RX PL (planname)	evaluate impact 81
command 130	lockout events (LKEVENT) 19
RX PT (planname) (owner)	trace log data sets 69, 101
command 132	Trace Summary by Time display 95
RX TB (tablename OBID)	Truce Summary by Time display
command 133	
RxD2	
accessing from other products 121	
using with MAINVIEW for DB2 111	
expand from DBIOD 128	
expand from DBIOR 129	

SQL	stop time
action	default timer request 28
COMMIT 114, 126	default trace request 62
ROLLBACK 114, 126	tutorial example 103
execute	stopping
tutorial example 114, 126	monitors 29
tutorial example	STORAGE keyword
full text of current statement 12, 122	default trace request 62
printing 120	I/O trace request 103
prototyping 112	STRAC
statement pop-up (DTRAC) 84, 119	display
statement pop-up (STRAC) 78, 126	tutorial example 72, 97, 138
statement summary (STRAC) 76, 82, 125	STRATE view
SQL Counts Detail view 16	tutorial example 9
SQLID	STSQLD view
current 115, 122, 126	tutorial example 16
SSI Context Activity Manager view 42	summary trace
SSI Context Selection List view 42	authorization ID
SSI Easy Menu 8, 35	tutorial example 99
ST application transfer	connection name
tutorial example 60, 113	tutorial example 99
START	day
keyword	tutorial example 99
default timer request 28	location name
default trace request 62	tutorial example 99
tutorial example 103	plan name
Start DB2 Trace Request	tutorial example 96
data entry panel 61	time
Start DB2 Workload Monitor Request	tutorial example 94, 100
data entry panel 27	Summary Trace Entry display
start time	tutorial example
default timer request 28	base section 72, 97
default trace request 62	buffer pool activity 74
tutorial example 103	database summary 79
starting	detail event summaries 76
monitors	
tutorial example 26, 27	elapsed time 73 lock and I/O events 80
trace	navigate 82
	_
tutorial example 60, 103, 113	package/DBRM overview 75 sort summary 81
of all DP2a 8	*
of all DB2s 8	SQL statement pop-up 78, 126 SQL statement summary 76, 82, 125
of current traces 60, 66 of one DB2 15	SYNC parameter
detail view 15	tutorial example 86
of thread completion 72	-
Status Detail - Interval view 15	syntax notation vii
STDB2 view	notation vii
tutorial example 8, 15	
STDB2D view	
tutorial example 15	
-	
STEXC view	
tutorial example 13	
STOP (7) line command, 20	
(Z) line command 29	
keyword	
default timer request 28	
default trace request 62	
tutorial example 103	

Т	threshold
tab points for expanding	marker 26, 32
tutorial examples	monitor history display 33
BIND-TEXT pop-up 118	warning message 28, 32
from DBIOD display 128	time
from DBIOR display 128, 129	command
from DTRAC display 118, 119	tutorial example 15
from DUSER display 122, 123	of exception
from LTRAC display 71, 85, 86	locate 38
from SQL statement pop-up 78, 126	TIME keyword
from TSTAT display 86	tutorial example 96, 98
from USERS display 122	title
to a subset of threads (LTRAC) 96	defining 62, 103
to buffer pool activity 74	TITLE keyword tutorial example 62, 103
to current trace log data set 100	trace
to database summary 79	tutorial example
to DB2 catalog information 128	accessing EXPLAIN 124
to DBIO display 86, 104	accessing services 70
to DBIOD display 128	activating 66
to DBIOP display 105	additional options 62
to DBIOS display 87	analyzing DB2 workload 93
to detail entry display (DTRAC) 83, 127	avoiding expensive lock event traces 81
to DTRAC display 118	BIND-TEXT pop-up 118
to DUSER display 122	buffer pool activity 74
to elapsed time analysis 73	collecting I/O events 103
to EXPLAIN PLAN_TABLE display 122, 123	database summary 79
to EXPLAIN pop-up 119	defaults 61
to lock and I/O events 80	detail entry display (DTRAC) 83, 118, 127
to LOCK-SUMMARY pop-up 119 to package details 75	detail event summaries 76
to sort summary 81	detail events 64, 103
to SQL statement pop-up 78, 84, 126	elapsed time 73
to SQL statement summary 76, 82, 125	error messages 66
to SQL statement text 78, 126	exception filters 63
to STRAC display 71, 97	EXPLAIN pop-up 119
to TSTAT display 85, 98	history 136
to TSUMP display 96	I/O analysis 86, 102
table administration	improving performance 67, 112
tutorial example	list of current 60, 69
access more details 133	list of historical data sets 69, 88, 101, 136
information for one table 133	list of trace entries (LTRAC) 71 lock and I/O events 80
table space	LOCK-SUMMARY pop-up 119
allocation	logging 65
balancing 25	long-running threads 69
catalog display 128	managing log data sets 88, 136
qualifier panel 129	narrowing 63
target	navigating 70, 82
when hyperlinking to RxD2 122, 130	package/DBRM overview 75
testing	Primary Option Menu selection 7, 60, 69
an application 67, 112	printing 88, 106, 136
an SQL statement 112, 114	qualifying 62
compare results 118	sort summary 81
tips 67, 112	SQL statement pop-up 78, 84, 126
THDACTV view	SQL statement summary 76, 82, 125
tutorial example 11 thread activity	starting 60, 103, 113
current 11	summary by authorization ID 99
multiple DB2s 13	summary by connection name 99
thread history	summary by DDF location 99
graphic display 94, 100	summary by plan 96
Dimpino dispinj > 1, 100	summary by relative day 99

trace (continued)	TYPE
tutorial example (continued)	keyword
summary by time 94, 100	tutorial example 62, 103
summary entry display (STRAC) 72, 97	
summary of all threads (TSTAT) 85, 98	
testing applications 67, 112	U
totals (TSTAT) 85, 98	user
tuning an application 59, 69	Detail Status display
Trace Statistics display	tutorial example 11, 122
tutorial example	warning messages sent to 28
base section 85, 98	UTRAC display
trace summary	view detail events as they occur
by authorization ID	tutorial example 69
tutorial example 99	r r
by connection name	
tutorial example 99	V
by location	volume
tutorial example 99	I/O analysis
by plan name	tutorial example 23
tutorial example 96	with data sharing 46
by relative day	Volume I/O SSI Summary - Session view 46
tutorial example 99	Volume I/O Summary - Session view 40 Volume I/O Summary - Session view 23, 46
by time	Volume Page Sets view 47
tutorial example 94, 100	volume rage sets view 47
TRANSFER command	
windows to full-screen mode	W
tutorial example 16	
transferring applications	W
tutorial examples 28, 30, 101	marker
CT command 113	graph of warning status 26, 32
LOG command 38, 99	monitor history display 33
SM command 26	warning
ST command 60, 113	all monitors 35
to full-screen mode 16	automatic 26, 28, 32
transferring between products	message
to other MAINVIEW products 34	current list 28
to RxD2 112, 121	hyperlink 9
expand from DBIOD 128	to a user 28
expand from DBIOR 129	to Journal log 28
TRBUFF	to the MVS console 28
Detail Trace Options panel	triggering AutoOPERATOR EXECs 28
tutorial example 64	tutorial example 13
trend	overview 32
of monitor history values 33, 36	status 26, 32
TRSIZE	threshold marker
Detail Trace Options panel	graph of warning status 26, 32
tutorial example 64	monitor history display 33
TSO id operand	threshold value
send warning messages to a user 28	starting a monitor 28
TSTAT	WHERE
display	command
tutorial example 85, 98	tutorial example 23
tutoriai example 83, 98	WIDTH keyword 141
E	WIF keyword
an application with trace 59, 69 group buffer pools 54	tutorial example 28
information	WIN keyword
	tutorial example 28
tutorial example 48	window
SQL prototyping 112	information line
print results 120	tutorial example 8

```
wizards
   tutorial example
      data sharing 47
      global lock 50
WLIM keyword
   tutorial example 28
WMSG keyword
   tutorial example
      starting a monitor 28
workload
   objectives
      monitoring 37
   service-level objective
      monitoring 37
workload history
   analyze
      navigate through trace displays 96
      past 100
      recent 94
workload monitors 27
workload selection criteria
   starting a monitor 28
WRAP keyword
   default trace request 62
WTO (write-to-operator operand)
   send messages to MVS console 28
WVAL keyword
   tutorial example
      starting a monitor 28
WZDSBOPT view
   tutorial example 55
WZDSDEP view
   tutorial example 47
WZDSGBR view
   tutorial example 56
WZDSGBRD view
   tutorial example 56
WZDSGBSA view
   tutorial example 57
WZDSGMEM view
   tutorial example 54
WZLKGCON view
   tutorial example 51
WZLKGMEM view
   tutorial example 51
WZLKGOPT view
   tutorial example 50
X
X ON|OFF command
   tutorial example 26, 34
Ζ
Z line command (STOP)
   tutorial example 29
```

Notes



100035978